
rasterio Documentation

Sean Gillies

Apr 12, 2024

CONTENTS

| | | |
|----------|---|-----------|
| 1 | Introduction | 3 |
| 1.1 | Philosophy | 3 |
| 1.2 | Rasterio license | 3 |
| 2 | Installation | 5 |
| 2.1 | Easy installation | 5 |
| 2.2 | Advanced installation | 5 |
| 3 | Python Quickstart | 7 |
| 3.1 | Opening a dataset in reading mode | 7 |
| 3.2 | Dataset attributes | 9 |
| 3.3 | Dataset georeferencing | 9 |
| 3.4 | Reading raster data | 10 |
| 3.5 | Spatial indexing | 11 |
| 3.6 | Creating data | 11 |
| 3.7 | Opening a dataset in writing mode | 12 |
| 3.8 | Saving raster data | 13 |
| 4 | Command Line User Guide | 15 |
| 4.1 | creation options | 16 |
| 4.2 | blocks | 16 |
| 4.3 | bounds | 17 |
| 4.4 | calc | 18 |
| 4.5 | clip | 18 |
| 4.6 | convert | 18 |
| 4.7 | edit-info | 19 |
| 4.8 | info | 20 |
| 4.9 | insp | 21 |
| 4.10 | mask | 22 |
| 4.11 | merge | 22 |
| 4.12 | overview | 22 |
| 4.13 | rasterize | 23 |
| 4.14 | rm | 23 |
| 4.15 | sample | 23 |
| 4.16 | shapes | 24 |
| 4.17 | stack | 24 |
| 4.18 | transform | 24 |
| 4.19 | warp | 25 |
| 4.20 | Rio Plugins | 25 |
| 4.21 | Other commands? | 26 |

| | |
|---|------------|
| 5 Advanced Topics | 27 |
| 5.1 Using rio-calc | 27 |
| 5.2 Color | 29 |
| 5.3 Concurrent processing | 31 |
| 5.4 GDAL Option Configuration | 34 |
| 5.5 Advanced Datasets | 35 |
| 5.6 Error Handling | 36 |
| 5.7 Vector Features | 36 |
| 5.8 Filling nodata areas | 38 |
| 5.9 Georeferencing | 38 |
| 5.10 Options | 40 |
| 5.11 Interoperability | 41 |
| 5.12 Masking a raster using a shapefile | 42 |
| 5.13 Nodata Masks | 43 |
| 5.14 In-Memory Files | 50 |
| 5.15 Migrating to Rasterio 1.0 | 52 |
| 5.16 Overviews | 56 |
| 5.17 Plotting | 57 |
| 5.18 Profiles and Writing Files | 63 |
| 5.19 Reading Datasets | 64 |
| 5.20 Reprojection | 67 |
| 5.21 Resampling | 71 |
| 5.22 Switching from GDAL's Python bindings | 73 |
| 5.23 Tagging datasets and bands | 79 |
| 5.24 Transforms | 80 |
| 5.25 Virtual Warping | 82 |
| 5.26 Virtual Filesystems | 85 |
| 5.27 Windowed reading and writing | 87 |
| 5.28 Writing Datasets | 92 |
| 6 Python API Reference | 95 |
| 6.1 rasterio package | 95 |
| 7 Contributing | 225 |
| 7.1 Code of Conduct | 225 |
| 7.2 Rights | 225 |
| 7.3 Issue Conventions | 225 |
| 7.4 Design Principles | 226 |
| 7.5 Dataset Objects | 226 |
| 7.6 Path Objects | 226 |
| 7.7 Band Objects | 226 |
| 7.8 GDAL Context | 226 |
| 7.9 Git Conventions | 227 |
| 7.10 Conventions | 227 |
| 7.11 New Containerized Development Environment | 227 |
| 7.12 Historical Development Environment | 227 |
| 7.13 Additional Information | 229 |
| 8 Frequently Asked Questions | 231 |
| 8.1 Where is “ERROR 4: Unable to open EPSG support file gcs.csv” coming from and what does it mean? | 231 |
| 8.2 Why can't rasterio find proj.db (rasterio versions < 1.2.0)? | 232 |
| 8.3 Why can't rasterio find proj.db (rasterio from PyPI versions >= 1.2.0)? | 232 |
| 9 Indices and Tables | 233 |

Python Module Index **235**

Index **237**

Geographic information systems use GeoTIFF and other formats to organize and store gridded raster datasets such as satellite imagery and terrain models. Rasterio reads and writes these formats and provides a Python API based on Numpy N-dimensional arrays and GeoJSON.

Here's an example program that extracts the GeoJSON shapes of a raster's valid data footprint.

```
import rasterio
import rasterio.features
import rasterio.warp

with rasterio.open('example.tif') as dataset:

    # Read the dataset's valid data mask as a ndarray.
    mask = dataset.dataset_mask()

    # Extract feature shapes and values from the array.
    for geom, val in rasterio.features.shapes(
        mask, transform=dataset.transform):

        # Transform shapes from the dataset's own coordinate
        # reference system to CRS84 (EPSG:4326).
        geom = rasterio.warp.transform_geom(
            dataset.crs, 'EPSG:4326', geom, precision=6)

    # Print GeoJSON shapes to stdout.
    print(geom)
```

The output of the program:

```
{'type': 'Polygon', 'coordinates': [[[(-77.730817, 25.282335), ...]]]}
```

Rasterio supports Python versions 3.6 or higher.

INTRODUCTION

1.1 Philosophy

Before Rasterio there was one Python option for accessing the many different kind of raster data files used in the GIS field: the Python bindings distributed with the [Geospatial Data Abstraction Library, GDAL](#). These bindings extend Python, but provide little abstraction for GDAL's C API. This means that Python programs using them tend to read and run like C programs. For example, GDAL's Python bindings require users to watch out for dangling C pointers, potential crashers of programs. This is bad: among other considerations we've chosen Python instead of C to avoid problems with pointers.

What would it be like to have a geospatial data abstraction in the Python standard library? One that used modern Python language features and idioms? One that freed users from concern about dangling pointers and other C programming pitfalls? Rasterio's goal is to be this kind of raster data library – expressing GDAL's data model using fewer non-idiomatic extension classes and more idiomatic Python types and protocols, while performing as fast as GDAL's Python bindings.

High performance, lower cognitive load, cleaner and more transparent code. This is what Rasterio is about.

1.2 Rasterio license

Copyright (c) 2016, MapBox All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of Mapbox nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL <COPYRIGHT HOLDER> BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

INSTALLATION

Installation of the Rasterio package is complicated by its dependency on libgdal and other C libraries. There are easy installations paths and an advanced installation path.

2.1 Easy installation

Rasterio has several [extension modules](#) which link against libgdal. This complicates installation. Binary distributions (wheels) containing libgdal and its own dependencies are available from the Python Package Index and can be installed using pip.

```
pip install rasterio
```

These wheels are mainly intended to make installation easy for simple applications, not so much for production. They are not tested for compatibility with all other binary wheels, conda packages, or QGIS, and omit many of GDAL's optional format drivers.

Many users find Anaconda and conda-forge a good way to install Rasterio and get access to more optional format drivers (like TileDB and others).

Rasterio 1.3 requires Python 3.8 or higher and GDAL 3.1 or higher.

2.2 Advanced installation

Once GDAL and its dependencies are installed on your computer (how to do this is documented at <https://gdal.org>) Rasterio can be built and installed using setuptools or pip. If your GDAL installation provides the `gdal-config` program, the process is simpler.

Without pip:

```
GDAL_CONFIG=/path/to/gdal-config python setup.py install
```

With pip (version >= 22.3 is required):

```
python -m pip install --user -U pip
GDAL_CONFIG=/path/to/gdal-config python -m pip install --user --no-binary rasterio
→ rasterio
```

These are pretty much equivalent. Pip will use setuptools as the build backend. If the `gdal-config` program is on your executable path, then you don't need to set the environment variable.

Without `gdal-config` you will need to configure header and library locations for the build in another way. One way to do this is to create a `setup.cfg` file in the source directory with content like this:

```
[build_ext]
```

```
include_dirs = C:/vcpkg/installed/x64-windows/include
libraries = gdal
library_dirs = C:/vcpkg/installed/x64-windows/lib
```

This is the approach taken by Rasterio's [wheel-building workflow](#). With this file in place you can run either `python setup.py install` or `python -m pip install --user ..`

You can also pass those three values on the command line following the [setuptools documentation](#). However, the `setup.cfg` approach is easier.


PYTHON QUICKSTART

Reading and writing data files is a spatial data programmer’s bread and butter. This document explains how to use Rasterio to read existing files and to create new files. Some advanced topics are glossed over to be covered in more detail elsewhere in Rasterio’s documentation. Only the GeoTIFF format is used here, but the examples do apply to other raster data formats. It is presumed that Rasterio has been [installed](#).

3.1 Opening a dataset in reading mode

Consider a GeoTIFF file named `example.tif` with 16-bit Landsat 8 imagery covering a part of the United States’s Colorado Plateau¹. Because the imagery is large (70 MB) and has a wide dynamic range it is difficult to display it in a browser. A rescaled and dynamically squashed version is shown below.

¹ “example.tif” is an alias for band 4 of Landsat scene LC80370342016194LGN00.



Import rasterio to begin.

```
>>> import rasterio
```

Next, open the file.

```
>>> dataset = rasterio.open('example.tif')
```

Rasterio's `open()` function takes a path string or path-like object and returns an opened dataset object. The path may point to a file of any supported raster format. Rasterio will open it using the proper GDAL format driver. Dataset objects have some of the same attributes as Python file objects.

```
>>> dataset.name
```

(continues on next page)

(continued from previous page)

```
'example.tif'
>>> dataset.mode
'r'
>>> dataset.closed
False
```

3.2 Dataset attributes

Properties of the raster data stored in the example GeoTIFF can be accessed through attributes of the opened dataset object. Dataset objects have bands and this example has a band count of 1.

```
>>> dataset.count
1
```

A dataset band is an array of values representing the partial distribution of a single variable in 2-dimensional (2D) space. All band arrays of a dataset have the same number of rows and columns. The variable represented by the example dataset's sole band is Level-1 digital numbers (DN) for the Landsat 8 Operational Land Imager (OLI) band 4 (wavelengths between 640-670 nanometers). These values can be scaled to radiance or reflectance values. The array of DN values is 7731 columns wide and 7871 rows high.

```
>>> dataset.width
7731
>>> dataset.height
7871
```

Some dataset attributes expose the properties of all dataset bands via a tuple of values, one per band. To get a mapping of band indexes to variable data types, apply a dictionary comprehension to the `zip()` product of a dataset's `indexes` and `dtypes` attributes.

```
>>> {i: dtype for i, dtype in zip(dataset.indexes, dataset.dtypes)}
{1: 'uint16'}
```

The example file's sole band contains unsigned 16-bit integer values. The GeoTIFF format also supports signed integers and floats of different size.

3.3 Dataset georeferencing

A GIS raster dataset is different from an ordinary image; its elements (or “pixels”) are mapped to regions on the earth’s surface. Every pixels of a dataset is contained within a spatial bounding box.

```
>>> dataset.bounds
BoundingBox(left=358485.0, bottom=4028985.0, right=590415.0, top=4265115.0)
```

Our example covers the world from 358485 meters (in this case) to 590415 meters, left to right, and 4028985 meters to 4265115 meters bottom to top. It covers a region 231.93 kilometers wide by 236.13 kilometers high.

The value of `bounds` attribute is derived from a more fundamental attribute: the dataset’s geospatial transform.

```
>>> dataset.transform  
Affine(30.0, 0.0, 358485.0,  
      0.0, -30.0, 4265115.0)
```

A dataset's `transform` is an affine transformation matrix that maps pixel locations in (row, col) coordinates to (x, y) spatial positions. The product of this matrix and (0, 0), the row and column coordinates of the upper left corner of the dataset, is the spatial position of the upper left corner.

```
>>> dataset.transform * (0, 0)  
(358485.0, 4265115.0)
```

The position of the lower right corner is obtained similarly.

```
>>> dataset.transform * (dataset.width, dataset.height)  
(590415.0, 4028985.0)
```

But what do these numbers mean? 4028985 meters from where? These coordinate values are relative to the origin of the dataset's coordinate reference system (CRS).

```
>>> dataset.crs  
CRS.from_epsg(32612)
```

“EPSG 32612” identifies a particular coordinate reference system: `UTM` zone 12N. This system is used for mapping areas in the Northern Hemisphere between 108 and 114 degrees west. The upper left corner of the example dataset, (358485.0, 4265115.0), is 141.5 kilometers west of zone 12’s central meridian (111 degrees west) and 4265 kilometers north of the equator.

Between the `crs` attribute and `transform` the georeferencing of a raster dataset is described and the dataset can compared to other GIS datasets.

3.4 Reading raster data

Data from a raster band can be accessed by the band's index number. Following the GDAL convention, bands are indexed from 1.

```
>>> dataset.indexes  
(1,)  
>>> band1 = dataset.read(1)
```

The `read()` method returns a Numpy N-D array.

```
>>> band1  
array([[0, 0, 0, ..., 0, 0, 0],  
       [0, 0, 0, ..., 0, 0, 0],  
       [0, 0, 0, ..., 0, 0, 0],  
       ...,  
       [0, 0, 0, ..., 0, 0, 0],  
       [0, 0, 0, ..., 0, 0, 0],  
       [0, 0, 0, ..., 0, 0, 0]], dtype=uint16)
```

Values from the array can be addressed by their row, column index.

```
>>> band1[dataset.height // 2, dataset.width // 2]
17491
```

3.5 Spatial indexing

Datasets have an `index()` method for getting the array indices corresponding to points in georeferenced space. To get the value for the pixel 100 kilometers east and 50 kilometers south of the dataset's upper left corner, do the following.

```
>>> x, y = (dataset.bounds.left + 100000, dataset.bounds.top - 50000)
>>> row, col = dataset.index(x, y)
>>> row, col
(1666, 3333)
>>> band1[row, col]
7566
```

To get the spatial coordinates of a pixel, use the dataset's `xy()` method. The coordinates of the center of the image can be computed like this.

```
>>> dataset.xy(dataset.height // 2, dataset.width // 2)
(476550.0, 4149150.0)
```


3.6 Creating data

Reading data is only half the story. Using Rasterio dataset objects, arrays of values can be written to a raster data file and thus shared with other GIS applications such as QGIS.

As an example, consider an array of floating point values representing, e.g., a temperature or pressure anomaly field measured or modeled on a regular grid, 240 columns by 180 rows. The first and last grid points on the horizontal axis are located at 4.0 degrees west and 4.0 degrees east longitude, the first and last grid points on the vertical axis are located at 3 degrees south and 3 degrees north latitude.

```
>>> import numpy as np
>>> x = np.linspace(-4.0, 4.0, 240)
>>> y = np.linspace(-3.0, 3.0, 180)
>>> X, Y = np.meshgrid(x, y)
>>> Z1 = np.exp(-2 * np.log(2) * ((X - 0.5) ** 2 + (Y - 0.5) ** 2) / 1 ** 2)
>>> Z2 = np.exp(-3 * np.log(2) * ((X + 0.5) ** 2 + (Y + 0.5) ** 2) / 2.5 ** 2)
>>> Z = 10.0 * (Z2 - Z1)
```

The fictional field for this example consists of the difference of two Gaussian distributions and is represented by the array Z. Its contours are shown below.



3.7 Opening a dataset in writing mode

To save this array along with georeferencing information to a new raster data file, call `rasterio.open()` with a path to the new file to be created, '`w`' to specify writing mode, and several keyword arguments.

- `driver`: the name of the desired format driver
- `width`: the number of columns of the dataset
- `height`: the number of rows of the dataset
- `count`: a count of the dataset bands
- `dtype`: the data type of the dataset
- `crs`: a coordinate reference system identifier or description
- `transform`: an affine transformation matrix, and
- `nodata`: a “nodata” value

The first 5 of these keyword arguments parametrize fixed, format-specific properties of the data file and are required when opening a file to write. The last 3 are optional.

In this example the coordinate reference system will be '`+proj=latlong`', which describes an equirectangular coordinate reference system with units of decimal degrees. The proper affine transformation matrix can be computed from the matrix product of a translation and a scaling.

```
>>> from rasterio.transform import Affine
>>> res = (x[-1] - x[0]) / 240.0
>>> transform = Affine.translation(x[0] - res / 2, y[0] - res / 2) * Affine.scale(res, -res)
>>> transform
Affine(0.03333333333333333, 0.0, -4.016666666666666,
      0.0, 0.03333333333333333, -3.016666666666666)
```

The upper left point in the example grid is at 3 degrees west and 2 degrees north. The raster pixel centered on this grid point extends `res / 2`, or 1/60 degrees, in each direction, hence the shift in the expression above.

A dataset for storing the example grid is opened like so

```
>>> new_dataset = rasterio.open(
...     '/tmp/new.tif',
...     'w',
...     driver='GTiff',
...     height=Z.shape[0],
...     width=Z.shape[1],
...     count=1,
...     dtype=Z.dtype,
...     crs='+proj=latlong',
...     transform=transform,
... )
```

Values for the `height`, `width`, and `dtype` keyword arguments are taken directly from attributes of the 2-D array, `Z`. Not all raster formats can support the 64-bit float values in `Z`, but the GeoTIFF format can.

3.8 Saving raster data

To copy the grid to the opened dataset, call the new dataset's `write()` method with the grid and target band number as arguments.

```
>>> new_dataset.write(Z, 1)
```

Then call the `close()` method to sync data to disk and finish.

```
>>> new_dataset.close()
```

Because Rasterio's dataset objects mimic Python's file objects and implement Python's context manager protocol, it is possible to do the following instead.

```
with rasterio.open(
    '/tmp/new.tif',
    'w',
    driver='GTiff',
    height=Z.shape[0],
    width=Z.shape[1],
    count=1,
    dtype=Z.dtype,
    crs='+proj=latlong',
    transform=transform,
```

(continues on next page)

(continued from previous page)

```
) as dst:  
    dst.write(Z, 1)
```

These are the basics of reading and writing raster data files. More features and examples are contained in the [advanced topics](#) section.

CHAPTER
FOUR

COMMAND LINE USER GUIDE

Rasterio's command line interface (CLI) is a program named "rio"¹.

The CLI allows you to build workflows using shell commands, either interactively at the command prompt or with a script. Many common cases are covered by CLI sub-commands and it is often more convenient to use a ready-made command as opposed to implementing similar functionality as a python script.

The rio program is developed using the [Click](#) framework. Its plugin system allows external modules to share a common namespace and handling of context variables.

```
$ rio --help
Usage: rio [OPTIONS] COMMAND [ARGS]...

  Rasterio command line interface.

Options:
  -v, --verbose            Increase verbosity.
  -q, --quiet              Decrease verbosity.
  --aws-profile TEXT       Select a profile from the AWS credentials file
  --aws-no-sign-requests  Make requests anonymously
  --aws-requester-pays    Requester pays data transfer costs
  --version                Show the version and exit.
  --gdal-version           Show this message and exit.

Commands:
  blocks      Write dataset blocks as GeoJSON features.
  bounds      Write bounding boxes to stdout as GeoJSON.
  calc        Raster data calculator.
  clip        Clip a raster to given bounds.
  convert     Copy and convert raster dataset.
  edit-info   Edit dataset metadata.
  env         Print information about the Rasterio environment.
  gcps       Print ground control points as GeoJSON.
  info        Print information about a data file.
  insp       Open a data file and start an interpreter.
  mask       Mask in raster using features.
  merge      Merge a stack of raster datasets.
  overview   Construct overviews in an existing dataset.
```

(continues on next page)

¹ In some Linux distributions "rio" may instead refer to the command line Diamond Rio MP3 player controller. This conflict can be avoided by installing Rasterio in an isolated Python environment.

(continued from previous page)

| | |
|-----------|---|
| rasterize | Rasterize features. |
| rm | Delete a dataset. |
| sample | Sample a dataset. |
| shapes | Write shapes extracted from bands or masks. |
| stack | Stack a number of bands into a multiband dataset. |
| transform | Transform coordinates. |
| warp | Warp a raster dataset. |

Commands are shown below. See --help of individual commands for more details.

4.1 creation options

For commands that create new datasets, format specific creation options may also be passed using --co. For example, to tile a new GeoTIFF output file, add the following.

```
--co tiled=true --co blockysize=256 --co blockxsize=256
```

To compress it using the LZW method, add

```
--co compress=LZW
```

4.2 blocks

This command prints features describing a raster's internal blocks, which are used directly for raster I/O. These features can be used to visualize how a windowed operation would operate using those blocks.

Output features have two JSON encoded properties: block and window. Block is a two element array like [0, 0] describing the window's position in the input band's window layout. Window is a JSON serialization of rasterio's Window class like {"col_off": 0, "height": 3, "row_off": 705, "width": 791}.

Block windows are extracted from the dataset (all bands must have matching block windows) by default, or from the band specified using the --bidx option:

```
rio blocks --bidx 3 tests/data/RGB.byte.tif
```

By default a GeoJSON FeatureCollection is written. With the --sequence option a GeoJSON feature stream is written instead.

```
rio blocks tests/data/RGB.byte.tif --sequence
```

Output features are reprojected to OGC:CRS84 (WGS 84) unless the --projected flag is provided, which causes the output to be kept in the input datasource's coordinate reference system.

For more information on exactly what blocks and windows represent, see `rasterio._base.DatasetBase.block_windows()`.

4.3 bounds

The `bounds` command writes the bounding boxes of raster datasets to GeoJSON for use with, e.g., `geojsonio-cli`.

```
$ rio bounds tests/data/RGB.byte.tif --indent 2
{
  "features": [
    {
      "geometry": {
        "coordinates": [
          [
            [
              [
                [
                  [
                    [
                      [
                        [
                          [
                            [
                              [
                                [
                                  [
                                    [
                                      [
                                        [
                                          [
                                            [
                                              [
                                                [
                                                  [
                                                    [
                                                      [
                                                        [
                                                          [
                                                            [
                                                              [
                                                                [
                                                                  [
                                                                    [
                                                                      [
                                                                        [
                                                                          [
                                                                            [
                                                                              [
                                                                                [
                                                                                  [
                                                                                    [
                                                                                      [
                                                                                      [
                                                                                      [
                                                                                      [
                                                                                      [
                                                                                      [
                                                                                      [
................................................................
```

Shoot the GeoJSON into a Leaflet map using `geojsonio-cli` by typing `rio bounds tests/data/RGB.byte.tif | geojsonio`.

4.4 calc

The `calc` command reads files as arrays, evaluates lisp-like expressions in their context, and writes the result as a new file. Members of the numpy module and arithmetic and logical operators are available builtin functions and operators. It is intended for simple calculations; any calculations requiring multiple steps is better done in Python using the Rasterio and Numpy APIs.

Input files may have different numbers of bands but should have the same number of rows and columns. The output file will have the same number of rows and columns as the inputs and one band per element of the expression result. An expression involving arithmetic operations on N-D arrays will produce a N-D array and result in an N-band output file.

The following produces a 3-band GeoTIFF with all values scaled by 0.95 and incremented by 2. In the expression, `(read 1)` evaluates to the first input dataset (3 bands) as a 3-D array.

```
$ rio calc "(+ 2 (* 0.95 (read 1)))" tests/data/RGB.byte.tif /tmp/out.tif
```

The following produces a 3-band GeoTIFF in which the first band is copied from the first band of the input and the next two bands are scaled (down) by the ratio of the first band's mean to their own means. The `--name` option is used to bind datasets to a name within the expression. `(take a 1)` gets the first band of the dataset named `a` as a 2-D array and `(asarray ...)` collects a sequence of 2-D arrays into a 3-D array for output.

```
$ rio calc "(asarray (take a 1) (* (take a 2) (/ (mean (take a 1)) (mean (take a 2))))\n  ↪(* (take a 3) (/ (mean (take a 1)) (mean (take a 3)))))" \  
 > --name a=tests/data/RGB.byte.tif /tmp/out.rgb.tif
```

The command above is also an example of a calculation that is far beyond the design of the `calc` command and something that could be done much more efficiently in Python.

4.5 clip

The `clip` command clips a raster using bounds input directly or from a template raster.

```
$ rio clip input.tif output.tif --bounds xmin ymin xmax ymax  
$ rio clip input.tif output.tif --like template.tif
```

If using `--bounds`, values must be in coordinate reference system of input. If using `--like`, bounds will automatically be transformed to match the coordinate reference system of the input.

It can also be combined to read bounds of a feature dataset using Fiona:

```
$ rio clip input.tif output.tif --bounds $(fio info features.shp --bounds)
```

4.6 convert

The `convert` command copies and converts raster datasets to other data types and formats (similar to `gdal_translate`).

Data values may be linearly scaled when copying by using the `--scale-ratio` and `--scale-offset` options. Destination raster values are calculated as

```
dst = scale_ratio * src + scale_offset
```

For example, to scale uint16 data with an actual range of 0-4095 to 0-255 as uint8:

```
$ rio convert in16.tif out8.tif --dtype uint8 --scale-ratio 0.0625
```

You can use `-rgb` as shorthand for `-co photometric=rgb`.

4.7 edit-info

The `edit-info` command allows you edit a raster dataset's metadata, namely

- coordinate reference system
- affine transformation matrix
- nodata value
- tags
- color interpretation

A TIFF created by spatially-unaware image processing software like Photoshop or Imagemagick can be turned into a GeoTIFF by editing these metadata items.

For example, you can set or change a dataset's coordinate reference system to Web Mercator (EPSG:3857),

```
$ rio edit-info --crs EPSG:3857 example.tif
```

set its *affine transformation matrix*,

```
$ rio edit-info --transform "[300.0, 0.0, 101985.0, 0.0, -300.0, 2826915.0]" example.tif
```

or set its nodata value to, e.g., 0:

```
$ rio edit-info --nodata 0 example.tif
```

or set its color interpretation to red, green, blue, and alpha:

```
$ rio edit-info --colorinterp 1=red,2=green,3=blue,4=alpha example.tif
```

which can also be expressed as:

```
$ rio edit-info --colorinterp RGBA example.tif
```

See `rasterio.enums.ColorInterp` for a full list of supported color interpretations and the color docs for more information.

4.8 info

The `info` command prints structured information about a dataset.

```
$ rio info tests/data/RGB.byte.tif --indent 2
{
  "count": 3,
  "crs": "EPSG:32618",
  "dtype": "uint8",
  "driver": "GTiff",
  "bounds": [
    101985.0,
    2611485.0,
    339315.0,
    2826915.0
  ],
  "lnglat": [
    -77.75790625255473,
    24.561583285327067
  ],
  "height": 718,
  "width": 791,
  "shape": [
    718,
    791
  ],
  "res": [
    300.0379266750948,
    300.041782729805
  ],
  "nodata": 0.0
}
```

More information, such as band statistics, can be had using the `--verbose` option.

```
$ rio info tests/data/RGB.byte.tif --indent 2 --verbose
{
  "count": 3,
  "crs": "EPSG:32618",
  "stats": [
    {
      "max": 255.0,
      "mean": 44.434478650699106,
      "min": 1.0
    },
    {
      "max": 255.0,
      "mean": 66.02203484105824,
      "min": 1.0
    },
    {
      "max": 255.0,
      "mean": 71.39316199120559,
```

(continues on next page)

(continued from previous page)

```

        "min": 1.0
    }
],
"dtype": "uint8",
"driver": "GTiff",
"bounds": [
    101985.0,
    2611485.0,
    339315.0,
    2826915.0
],
"lnglat": [
    -77.75790625255473,
    24.561583285327067
],
"height": 718,
"width": 791,
"shape": [
    718,
    791
],
"res": [
    300.0379266750948,
    300.041782729805
],
"nodata": 0.0
}

```

4.9 insp

The `insp` command opens a dataset and an interpreter.

```
$ rio insp --ipython tests/data/RGB.byte.tif
Rasterio 0.32.0 Interactive Inspector (Python 2.7.10)
Type "src.meta", "src.read(1)", or "help(src)" for more information.
In [1]: print(src.name)
/path/rasterio/tests/data/RGB.byte.tif

In [2]: print(src.bounds)
BoundingBox(left=101985.0, bottom=2611485.0, right=339315.0, top=2826915.0)
```

4.10 mask

The `mask` command masks in pixels from all bands of a raster using features (masking out all areas not covered by features) and optionally crops the output raster to the extent of the features. Features are assumed to be in the same coordinate reference system as the input raster.

A common use case is masking in raster data by political or other boundaries.

```
$ rio mask input.tif output.tif --geojson-mask input.geojson
```

GeoJSON features may be provided using stdin or specified directly as first argument, and output can be cropped to the extent of the features.

```
$ rio mask input.tif output.tif --crop --geojson-mask - < input.geojson
```

The feature mask can be inverted to mask out pixels covered by features and keep pixels not covered by features.

```
$ rio mask input.tif output.tif --invert --geojson-mask input.geojson
```

4.11 merge

The `merge` command can be used to flatten a stack of identically structured datasets.

```
$ rio merge rasterio/tests/data/R*.tif merged.tif
```

4.12 overview

The `overview` command creates overviews stored in the dataset, which can improve performance in some applications.

The decimation levels at which to build overviews can be specified as a comma separated list

```
$ rio overview --build 2,4,8,16
```

or a base and range of exponents.

```
$ rio overview --build 2^1..4
```

Note that overviews can not currently be removed and are not automatically updated when the dataset's primary bands are modified.

Information about existing overviews can be printed using the `-ls` option.

```
$ rio overview --ls
```

The block size (tile width and height) used for overviews (internal or external) can be specified by setting the `GDAL_TIFF_OVR_BLOCKSIZE` environment variable to a power-of-two value between 64 and 4096. The default value is 128.

```
$ GDAL_TIFF_OVR_BLOCKSIZE=256 rio overview --build 2^1..4
```

4.13 rasterize

The `rasterize` command rasterizes GeoJSON features into a new or existing raster.

```
$ rio rasterize test.tif --res 0.0167 < input.geojson
```

The resulting file will have an upper left coordinate determined by the bounds of the GeoJSON (in EPSG:4326, which is the default), with a pixel size of approximately 30 arc seconds. Pixels whose center is within the polygon or that are selected by Bresenham's line algorithm will be burned in with a default value of 1.

It is possible to rasterize into an existing raster and use an alternative default value:

```
$ rio rasterize existing.tif --default_value 10 < input.geojson
```

It is also possible to rasterize using a template raster, which will be used to determine the transform, dimensions, and coordinate reference system of the output raster:

```
$ rio rasterize test.tif --like tests/data/shade.tif < input.geojson
```

GeoJSON features may be provided using stdin or specified directly as first argument, and dimensions may be provided in place of pixel resolution:

```
$ rio rasterize input.geojson test.tif --dimensions 1024 1024
```

Other options are available, see:

```
$ rio rasterize --help
```

4.14 rm

Invoking the shell's `$ rm <path>` on a dataset can be used to delete a dataset referenced by a file path, but it won't handle deleting side car files. This command is aware of datasets and their sidecar files.

4.15 sample

The `sample` command reads x, y positions from stdin and writes the dataset values at that position to stdout.

```
$ cat << EOF | rio sample tests/data/RGB.byte.tif
> [220649.99999832606, 2719199.999999095]
> EOF
[18, 25, 14]
```

The output of the `transform` command (see below) makes good input for `sample`.

4.16 shapes

The `shapes` command extracts and writes features of a specified dataset band out as GeoJSON.

```
$ rio shapes tests/data/shade.tif --bidx 1 --precision 6 --collection > shade.geojson
```

The resulting file looks [like this](#).

Using the `--mask` option you can write out the shapes of a dataset's valid data region.

```
$ rio shapes tests/data/RGB.byte.tif --mask --precision 6 --collection > mask.geojson
```

The output of which looks [like this](#).

Note: `rio shapes` returns line-delimited GeoJSONs by default. Use the `--collection` flag as shown here to return a single GeoJSON feature collection.

4.17 stack

The `stack` command stacks a number of bands from one or more input files into a multiband dataset. Input datasets must be of a kind: same data type, dimensions, etc. The output is cloned from the first input. By default, `stack` will take all bands from each input and write them in same order to the output. Optionally, bands for each input may be specified using the following syntax:

- `--bidx N` takes the Nth band from the input (first band is 1).
- `--bidx M,N,O` takes bands M, N, and O.
- `--bidx M..O` takes bands M-O, inclusive.
- `--bidx ..N` takes all bands up to and including N.
- `--bidx N..` takes all bands from N to the end.

Examples using the Rasterio testing dataset that produce a copy of it.

```
$ rio stack RGB.byte.tif stacked.tif
$ rio stack RGB.byte.tif --bidx 1,2,3 stacked.tif
$ rio stack RGB.byte.tif --bidx 1..3 stacked.tif
$ rio stack RGB.byte.tif --bidx ..2 RGB.byte.tif --bidx 3.. stacked.tif
```

You can use `-rgb` as shorthand for `-co photometric=rgb`.

4.18 transform

The `transform` command reads a JSON array of coordinates, interleaved, and writes another array of transformed coordinates to stdout.

To transform a longitude, latitude point (EPSG:4326 is the default) to another coordinate system with 2 decimal places of output precision, do the following.

```
$ echo "[-78.0, 23.0]" | rio transform --dst-crs EPSG:32618 --precision 2
[192457.13, 2546667.68]
```

To transform a longitude, latitude bounding box to the coordinate system of a raster dataset, do the following.

```
$ echo "[-78.0, 23.0, -76.0, 25.0]" | rio transform --dst-crs tests/data/RGB.byte.tif -  
-precision 2  
[192457.13, 2546667.68, 399086.97, 2765319.94]
```

4.19 warp

The `warp` command warps (reprojects) a raster based on parameters that can be obtained from a template raster, or input directly. The output is always overwritten.

To copy coordinate reference system, transform, and dimensions from a template raster, do the following:

```
$ rio warp input.tif output.tif --like template.tif
```

You can specify an output coordinate system using a PROJ.4 or EPSG:nnnn string, or a JSON text-encoded PROJ.4 object:

```
$ rio warp input.tif output.tif --dst-crs EPSG:4326
```

```
$ rio warp input.tif output.tif --dst-crs '+proj=longlat +ellps=WGS84 +datum=WGS84'
```

You can also specify dimensions, which will automatically calculate appropriate resolution based on the relationship between the bounds in the target crs and these dimensions:

```
$ rio warp input.tif output.tif --dst-crs EPSG:4326 --dimensions 100 200
```

Or provide output bounds (in source crs) and resolution:

```
$ rio warp input.tif output.tif --dst-crs EPSG:4326 --bounds -78 22 -76 24 --res 0.1
```

Previous command in case of south-up image, -- escapes the next -:

```
$ rio warp input.tif output.tif --dst-crs EPSG:4326 --bounds -78 22 -76 24 --res 0.1 -- -  
-0.1
```

Other options are available, see:

```
$ rio warp --help
```

4.20 Rio Plugins

Rio uses `click-plugins` to provide the ability to create additional subcommands using plugins developed outside rasterio. This is ideal for commands that require additional dependencies beyond those used by rasterio, or that provide functionality beyond the intended scope of rasterio.

For example, `rio-mbtiles` provides a command `rio mbtiles` to export a raster to an MBTiles file.

See `click-plugins` for more information on how to build these plugins in general.

To use these plugins with rio, add the commands to the `rasterio.rio_plugins` entry point in your `setup.py` file, as described [here](#) and in `rasterio/rio/main.py`.

See the `plugin registry` for a list of available plugins.

4.21 Other commands?

Suggestions for other commands are welcome!

ADVANCED TOPICS

5.1 Using rio-calc

Simple raster data processing on the command line is possible using Rasterio's rio-calc command. It uses the snuggs Numpy S-expression engine. The snuggs [README](#) explains how expressions are written and evaluated in general. This document explains Rasterio-specific details of rio-calc and offers some examples.

5.1.1 Expressions

Rio-calc expressions look like

```
(func|operator arg [*args])
```

where `func` may be the name of any function in the module `numpy` or one of the rio-calc builtins: `read`, `fillnodata`, or `sieve`; and `operator` may be any of the standard Python arithmetic or logical operators. The arguments may themselves be expressions.

5.1.2 Copying a file

Here's a trivial example of copying a dataset. The expression `(read 1)` evaluates to all bands of the first input dataset, an array with shape `(3, 718, 791)` in this case.

Note: rio-calc's indexes start at 1.

```
$ rio calc "(read 1)" tests/data/RGB.byte.tif out.tif
```

5.1.3 Reversing the band order of a file

The expression `(read i j)` evaluates to the `j`-th band of the `i`-th input dataset. The `asarray` function collects bands read in reverse order into an array with shape `(3, 718, 791)` for output.

```
$ rio calc "(asarray (read 1 3) (read 1 2) (read 1 1))" tests/data/RGB.byte.tif out.tif
```

5.1.4 Stacking bands of multiple files

Bands can be read from multiple input files. This example is another (slower) way to copy a file.

```
$ rio calc "(asarray (read 1 1) (read 2 2) (read 3 3))" \
> tests/data/RGB.byte.tif tests/data/RGB.byte.tif tests/data/RGB.byte.tif \
> out.tif
```

5.1.5 Named datasets

Datasets can be referenced in expressions by name and single bands picked out using the `take` function.

```
$ rio calc "(asarray (take a 3) (take a 2) (take a 1))" \
> --name "a=tests/data/RGB.byte.tif" out.tif
```

The third example, re-done using names, is:

```
$ rio calc "(asarray (take a 1) (take b 2) (take b 3))" \
> --name "a=tests/data/RGB.byte.tif" --name "b=tests/data/RGB.byte.tif" \
> --name "c=tests/data/RGB.byte.tif" out.tif
```

5.1.6 Read and take

The functions `read` and `take` overlap a bit in the previous examples but are rather different. The former involves I/O and the latter does not. You may also `take` from any array, as in this example.

```
$ rio calc "(take (read 1) 1)" tests/data/RGB.byte.tif out.tif
```

5.1.7 Arithmetic operations

Arithmetic operations can be performed as with Numpy. Here is an example of scaling all three bands of a dataset by the same factors.

```
$ rio calc "(+ 2 (* 0.95 (read 1)))" tests/data/RGB.byte.tif out.tif
```

Here is a more complicated example of scaling bands by different factors.

```
$ rio calc "(asarray (+ 2 (* 0.95 (read 1 1))) (+ 3 (* 0.9 (read 1 2))) (+ 4 (* 0.85 \
->(read 1 3))))" tests/data/RGB.byte.tif out.tif
```

5.1.8 Logical operations

Logical operations can be used in conjunction with arithmetic operations. In this example, the output values are 255 wherever the input values are greater than or equal to 40.

```
$ rio calc "(* (>= (read 1) 40) 255)" tests/data/RGB.byte.tif out.tif
```

5.2 Color

5.2.1 Color interpretation

Color interpretation of raster bands can be read from the dataset

```
>>> import rasterio
>>> src = rasterio.open("tests/data/RGB.byte.tif")
>>> src.colorinterp[0]
<ColorInterp.red: 3>
```

GDAL builds the color interpretation based on the driver and creation options. With the GTiff driver, rasters with exactly 3 bands of uint8 type will be RGB, 4 bands of uint8 will be RGBA by default.

Color interpretation can be set when creating a new datasource with the `photometric` creation option:

```
>>> profile = src.profile
>>> profile['photometric'] = "RGB"
>>> with rasterio.open("/tmp/rgb.tif", 'w', **profile) as dst:
...     dst.write(src.read())
```

or via the `colorinterp` property when a datasource is opened in update mode:

```
>>> from rasterio.enums import ColorInterp
>>> with rasterio.open('/tmp/rgb.tif', 'r+', **profile) as src:
...     src.colorinterp = [
...         ColorInterp.red, ColorInterp.green, ColorInterp.blue]
```

And the resulting raster will be interpreted as RGB.

```
>>> with rasterio.open("/tmp/rgb.tif") as src2:
...     src2.colorinterp[1]
<ColorInterp.green: 4>
```

5.2.2 Writing colormaps

Mappings from 8-bit (`rasterio.uint8`) pixel values to RGBA values can be attached to bands using the `write_colormap()` method.

```
import rasterio

with rasterio.Env():

    with rasterio.open('tests/data/shade.tif') as src:
        shade = src.read(1)
        meta = src.meta

    with rasterio.open('/tmp/colormap.tif', 'w', **meta) as dst:
        dst.write(shade, indexes=1)
        dst.write_colormap(
            1, {
                0: (255, 0, 0, 255),
```


(continues on next page)

(continued from previous page)

```
    255: (0, 0, 255, 255) })
cmap = dst.colormap(1)
# True
assert cmap[0] == (255, 0, 0, 255)
# True
assert cmap[255] == (0, 0, 255, 255)

subprocess.call(['open', '/tmp/colormap.tif'])
```

The program above (on OS X, another viewer is needed with a different OS) yields the image below:



5.2.3 Reading colormaps

As shown above, the `colormap()` returns a dict holding the colormap for the given band index. For TIFF format files, the colormap will have 256 items, and all but two of those would map to (0, 0, 0, 0) in the example above.

5.3 Concurrent processing

Rasterio affords concurrent processing of raster data. Python's global interpreter lock (GIL) is released when calling GDAL's `GDALRasterIO()` function, which means that Python threads can read and write concurrently.

The Numpy library also often releases the GIL, e.g., in applying universal functions to arrays, and this makes it possible to distribute processing of an array across cores of a processor.

This means that it is possible to parallelize tasks that need to be performed for a set of windows/pixels in the raster. Reading, writing and processing can always be done concurrently. But it depends on the hardware and where the bottlenecks are, how much of a speedup can be obtained. In the case that the processing function releases the GIL, multiple threads processing simultaneously can lead to further speedups.

Note: If you wish to do multiprocessing that is not trivially parallelizable accross very large images that do not fit in memory, or if you wish to do multiprocessing across multiple machines. You might want to have a look at [dask](#) and in particular this [example](#).

The Cython function below, included in Rasterio's `_example` module, simulates a GIL-releasing CPU-intensive raster processing function. You can also easily create GIL-releasing functions by using `numba`

```
# cython: boundscheck=False

import numpy as np

def compute(unsigned char[:, :, :] input):
    """reverses bands inefficiently

    Given input and output uint8 arrays, fakes an CPU-intensive
    computation.
    """
    cdef int I, J, K
    cdef int i, j, k, l
    cdef double val
    I = input.shape[0]
    J = input.shape[1]
    K = input.shape[2]
    output = np.empty((I, J, K), dtype='uint8')
    cdef unsigned char[:, :, :] output_view = output
    with nogil:
        for i in range(I):
            for j in range(J):
                for k in range(K):
                    val = <double>input[i, j, k]
                    for l in range(2000):
                        val += 1.0
                    val -= 2000.0
```

(continues on next page)

(continued from previous page)

```
    output_view[~i, j, k] = <unsigned char>val
return output
```

Here is the program in examples/thread_pool_executor.py. It is set up in such a way that at most 1 thread is reading and at most 1 thread is writing at the same time. Processing is not protected by a lock and can be done by multiple threads simultaneously.

```
"""thread_pool_executor.py

Operate on a raster dataset window-by-window using a ThreadPoolExecutor.

Simulates a CPU-bound thread situation where multiple threads can improve
performance.

With -j 4, the program returns in about 1/4 the time as with -j 1.

"""

import concurrent.futures
import multiprocessing
import threading

import rasterio
from rasterio._example import compute

def main(infile, outfile, num_workers=4):
    """Process infile block-by-block and write to a new file

    The output is the same as the input, but with band order
    reversed.
    """

    with rasterio.open(infile) as src:

        # Create a destination dataset based on source params. The
        # destination will be tiled, and we'll process the tiles
        # concurrently.
        profile = src.profile
        profile.update(blockxsize=128, blockysize=128, tiled=True)

        with rasterio.open(outfile, "w", **src.profile) as dst:
            windows = [window for ij, window in dst.block_windows()]

            # We cannot write to the same file from multiple threads
            # without causing race conditions. To safely read/write
            # from multiple threads, we use a lock to protect the
            # DatasetReader/Writer
            read_lock = threading.Lock()
            write_lock = threading.Lock()

            def process(window):
                with read_lock:
```

(continues on next page)

(continued from previous page)

```

src_array = src.read(window=window)

# The computation can be performed concurrently
result = compute(src_array)

with write_lock:
    dst.write(result, window=window)

# We map the process() function over the list of
# windows.
with concurrent.futures.ThreadPoolExecutor(
    max_workers=num_workers
) as executor:
    executor.map(process, windows)

```

The code above simulates a CPU-intensive calculation that runs faster when spread over multiple cores using the `ThreadPoolExecutor` from Python 3's `concurrent.futures` module. Compared to the case of one concurrent job (`-j 1`),

```
$ time python examples/thread_pool_executor.py tests/data/RGB.byte.tif /tmp/test.tif -j 1

real    0m4.277s
user    0m4.356s
sys     0m0.184s
```

we get over 3x speed up with four concurrent jobs.

```
$ time python examples/thread_pool_executor.py tests/data/RGB.byte.tif /tmp/test.tif -j 4

real    0m1.251s
user    0m4.402s
sys     0m0.168s
```

If the function that you'd like to map over raster windows doesn't release the GIL, you unfortunately cannot simply replace `ThreadPoolExecutor` with `ProcessPoolExecutor`, the DatasetReader/Writer cannot be shared by multiple processes, which means that each process needs to open the file separately, or you can do all the reading and writing from the main thread, as shown in this next example. This is much less efficient memory wise, however.

```

arrays = [src.read(window=window) for window in windows]

with concurrent.futures.ProcessPoolExecutor(
    max_workers=num_workers
) as executor:
    futures = executor.map(compute, arrays)
    for window, result in zip(windows, futures):
        dst.write(result, window=window)

```

5.4 GDAL Option Configuration

GDAL format drivers and some parts of the library are configurable.

From <https://trac.osgeo.org/gdal/wiki/ConfigOptions>:

ConfigOptions are normally used to alter the default behavior of GDAL and OGR drivers and in some cases the GDAL and OGR core. They are essentially global variables the user can set.

5.4.1 GDAL Example

The following is from GDAL's test suite.

```
gdal.SetConfigOption('GTIFF_FORCE_RGBA', 'YES')
ds = gdal.Open('data/stefan_full_greyalpha.tif')
gdal.SetConfigOption('GTIFF_FORCE_RGBA', None)
```

With GDAL's C or Python API, you call a function once to set a global configuration option before you need it and once again after you're through to unset it.

Downsides of this style of configuration include:

- Options can be configured far from the code they affect.
- There is no API for finding what options are currently set.
- If `gdal.Open()` raises an exception in the code above, the `GTIFF_FORCE_RGBA` option will not be unset.

That code example can be generalized to multiple options and made to recover better from errors.

```
options = {'GTIFF_FORCE_RGBA': 'YES'}
for key, val in options.items():
    gdal.SetConfigOption(key, val)
try:
    ds = gdal.Open('data/stefan_full_greyalpha.tif')
finally:
    for key, val in options.items():
        gdal.SetConfigOption(key, None)
```

This is better, but has a lot of boilerplate. Rasterio uses elements of Python syntax, keyword arguments and the `with` statement, to make this cleaner and easier to use.

5.4.2 Rasterio

```
with rasterio.Env(GTIFF_FORCE_RGBA=True, CPL_DEBUG=True):
    with rasterio.open('data/stefan_full_greyalpha.tif') as dataset:
        # Suite of code accessing dataset ``ds`` follows...
```

The object returned when you call `rasterio.Env()` is a context manager. It handles the GDAL configuration for a specific block of code and resets the configuration when the block exits for any reason, success or failure. The Rasterio `with rasterio.Env()` pattern organizes GDAL configuration into single statements and makes its relationship to a block of code clear.

If you want to know what options are configured at any time, you could bind it to a name like so.

```

with rasterio.Env(GTIFF_FORCE_RGBA=True, CPL_DEBUG=True) as env:
    for key, val in env.options.items():
        print(key, val)

# Prints:
# ('GTIFF_FORCE_RGBA', True)
# ('CPL_DEBUG', True)

```

5.4.3 When to use rasterio.Env()

Rasterio code is often without the use of an Env context block. For instance, you could use `rasterio.open()` directly without explicitly creating an Env. In that case, the `open` function will initialize a default environment in which to execute the code. Often this default environment is sufficient for most use cases and you only need to create an explicit Env if you are customizing the default GDAL or format options.

5.5 Advanced Datasets

The analogy of Python file objects influences the design of Rasterio dataset objects. Datasets of a few different kinds exist and the canonical way to obtain one is to call `rasterio.open` with a path-like object or URI-like identifier, a mode (such as “r” or “w”), and other keyword arguments.

5.5.1 Dataset Identifiers

Datasets in a computer’s filesystem are identified by paths, “file” URLs, or instances of `pathlib.Path`. The following are equivalent.

- `'/path/to/file.tif'`
- `'file:///path/to/file.tif'`
- `pathlib.Path('/path/to/file.tif')`

Datasets within a local zip file are identified using the “zip” scheme from [Apache Commons VFS](#).

- `'zip:///path/to/file.zip!/folder/file.tif'`
- `'zip+file:///path/to/file.zip!/folder/file.tif'`

Note that ! is the separator between the path of the archive file and the path within the archive file. Also note that this kind of identifier can’t be expressed using `pathlib`.

Similarly, variables of a netCDF dataset can be accessed using “netcdf” scheme identifiers.

`'netcdf:/path/to/file.nc:variable'`

Datasets on the web are identified by “http” or “https” URLs such as

- `'https://example.com/file.tif'`
- `'https://landsat-pds.s3.amazonaws.com/L8/139/045/LC81390452014295LGN00/LC81390452014295LGN00_B1.TIF'`

Datasets within a zip file on the web are identified using a “zip+https” scheme and paths separated by ! as above. For example:

`'zip+https://example.com/file.tif&p=x&q=y!/folder/file.tif'`

Datasets on AWS S3 may be identified using “s3” scheme identifiers.

```
's3://landsat-pds/L8/139/045/LC81390452014295LGN00/LC81390452014295LGN00_B1.TIF'
```

Resources in other cloud storage systems will be similarly supported.

5.6 Error Handling

Todo: error enums, context managers, converting GDAL errors to python exceptions

5.7 Vector Features

Rasterio’s `features` module provides functions to extract shapes of raster features and to create new features by “burning” shapes into rasters: `shapes()` and `rasterize()`. These functions expose GDAL functions in a general way, using iterators over GeoJSON-like Python objects instead of GIS layers.

5.7.1 Extracting shapes of raster features

Consider the Python logo.



The shapes of the foreground features can be extracted like this:

```
import pprint
import rasterio
from rasterio import features

with rasterio.open('13547682814_f2e459f7a5_o_d.png') as src:
    blue = src.read(3)

mask = blue != 255
shapes = features.shapes(blue, mask=mask)
pprint.pprint(next(shapes))

# Output
# pprint.pprint(next(shapes))
# {'coordinates': [[(71.0, 6.0),
# #                  (71.0, 7.0),
```

(continues on next page)

(continued from previous page)

```
#           (72.0, 7.0),
#           (72.0, 6.0),
#           (71.0, 6.0)]],
#   'type': 'Polygon'},
# 253)
```

The shapes iterator yields `geometry`, `value` pairs. The second item is the value of the raster feature corresponding to the shape and the first is its geometry. The coordinates of the geometries in this case are in pixel units with origin at the upper left of the image. If the source dataset was georeferenced, you would get similarly georeferenced geometries like this:

```
shapes = features.shapes(blue, mask=mask, transform=src.transform)
```

5.7.2 Burning shapes into a raster

To go the other direction, use `rasterize()` to burn values into the pixels intersecting with geometries.

```
image = features.rasterize(
    ((g, 255) for g, v in shapes),
    out_shape=src.shape)
```

By default, only pixels whose center is within the polygon or that are selected by Bresenham's line algorithm will be burned in. You can specify `all_touched=True` to burn in all pixels touched by the geometry. The geometries will be rasterized by the “painter’s algorithm” - geometries are handled in order and later geometries will overwrite earlier values.


Again, to burn in georeferenced shapes, pass an appropriate transform for the image to be created.

```
image = features.rasterize(
    ((g, 255) for g, v in shapes),
    out_shape=src.shape,
    transform=src.transform)
```

The values for the input shapes are replaced with 255 in a generator expression. Areas not covered by input geometries are replaced with an optional `fill` value, which defaults to 0. The resulting image, written to disk like this,

```
with rasterio.open(
    '/tmp/rasterized-results.tif', 'w',
    driver='GTiff',
    dtype=rasterio.uint8,
    count=1,
    width=src.width,
    height=src.height) as dst:
    dst.write(image, indexes=1)
```

has a black background and white foreground features.



5.8 Filling nodata areas

Todo: fillnodata()

5.9 Georeferencing

There are two parts to the georeferencing of raster datasets: the definition of the local, regional, or global system in which a raster's pixels are located; and the parameters by which pixel coordinates are transformed into coordinates in that system.

5.9.1 Coordinate Reference System

The coordinate reference system of a dataset is accessed from its `crs` attribute.

```
>>> import rasterio
>>> src = rasterio.open('tests/data/RGB.byte.tif')
>>> src.crs
CRS({'init': 'epsg:32618'})
```

Rasterio follows pyproj and uses PROJ.4 syntax in dict form as its native CRS syntax. If you want a WKT representation of the CRS, see the CRS class's `wkt` attribute.

```
>>> src.crs.wkt
'PROJCS["WGS 84 / UTM zone 18N",GEOGCS["WGS 84",DATUM["WGS_1984",SPHEROID["WGS 84",
    -6378137,298.257223563,AUTHORITY["EPSG","7030"]],AUTHORITY["EPSG","6326"]],PRIMEM[
    "Greenwich",0,AUTHORITY["EPSG","8901"]],UNIT["degree",0.0174532925199433,AUTHORITY[
    "EPSG","9122"]],AUTHORITY["EPSG","4326"]],PROJECTION["Transverse_Mercator"],PARAMETER[
    "latitude_of_origin",0],PARAMETER["central_meridian",-75],PARAMETER["scale_factor",0.
    9996],PARAMETER["false_easting",500000],PARAMETER["false_northing",0],UNIT["metre",1,
    AUTHORITY["EPSG","9001"]],AXIS["Easting",EAST],AXIS["Northing",NORTH],AUTHORITY["EPSG",
    "32618"]]'
```

When opening a new file for writing, you may also use a CRS string as an argument.

```
>>> profile = {'driver': 'GTiff', 'height': 100, 'width': 100, 'count': 1, 'dtype':_
... rasterio.uint8}
>>> with rasterio.open('/tmp/foo.tif', 'w', crs='EPSG:3857', **profile) as dst:
...     pass # write data to this Web Mercator projection dataset.
```

5.9.2 Coordinate Transformation

This section describes the three primary kinds of georeferencing metadata supported by rasterio.

Affine

A dataset's pixel coordinate system has its origin at the “upper left” (imagine it displayed on your screen). Column index increases to the right, and row index increases downward. The mapping of these coordinates to “world” coordinates in the dataset's reference system is typically done with an affine transformation matrix.

```
>>> src.transform
Affine(300.0379266750948, 0.0, 101985.0,
      0.0, -300.041782729805, 2826915.0)
```

The `Affine` object is a named tuple with elements `a`, `b`, `c`, `d`, `e`, `f` corresponding to the elements in the matrix equation below, in which a pixel's image coordinates are x , y and its world coordinates are x' , y' :

$$\begin{vmatrix} x' \\ y' \\ 1 \end{vmatrix} = \begin{vmatrix} a & b & c \\ d & e & f \\ 0 & 0 & 1 \end{vmatrix} \begin{vmatrix} x \\ y \\ 1 \end{vmatrix}$$

The `Affine` class has some useful properties and methods described at <https://github.com/sgillies/affine>.

Some datasets may not have an affine transformation matrix, but are still georeferenced.

Ground Control Points

A ground control point (GCP) is the mapping of a dataset's row and pixel coordinate to a single world x , y , and optionally z coordinate. Typically a dataset will have multiple GCPs distributed across the image. Rasterio can calculate an affine transformation matrix from a collection of GCPs using the `rasterio.transform.from_gcps` method. Alternatively GCP interpolation can also be used for coordinate transforms.

Rational Polynomial Coefficients

A dataset may also be georeferenced with a set of rational polynomial coefficients (RPCs) which can be used to compute pixel coordinates from x , y , and z coordinates. The RPCs are an application of the Rigorous Projection Model which uses four sets of 20 term cubic polynomials and several normalizing parameters to establish a relationship between image and world coordinates. RPCs are defined with image coordinates in pixel units and world coordinates in decimal degrees of longitude and latitude and height above the WGS84 ellipsoid (EPSG:4326).

RPCs are usually provided by the dataset provider and are only well behaved over the extent of the image. Additionally, accurate height values are required for the best results. Datasets with low terrain variation may use an average height over the extent of the image, while datasets with higher terrain variation should use a digital elevation model to sample height values. The coordinate transformation from world to pixel coordinates is exact while the reverse is not, and must

be computed iteratively. For more details on coordinate transformations using RPCs see https://gdal.org/api/gdal_alg.html#_CPPv424GDALCreateRPCTransformerP11GDALRPCInfoidPPc

5.10 Options

GDAL's format drivers have many configuration options. These options come in two flavors:

- **Configuration options** are used to alter the default behavior of GDAL and OGR and are generally treated as global environment variables by GDAL. These are set through a `rasterio.Env()` context block in Python.
- **Creation options** are passed into the driver at dataset creation time as keyword arguments to `rasterio.open(mode='w')`.

5.10.1 Configuration Options

GDAL options are typically set as environment variables. While environment variables will influence the behavior of `rasterio`, we highly recommend avoiding them in favor of defining behavior programmatically.

The preferred way to set options for `rasterio` is via `rasterio.Env()`. Options set on entering the context are deleted on exit.

```
import rasterio

with rasterio.Env(GDAL_TIFF_INTERNAL_MASK=True):
    # GeoTIFFs written here will have internal masks, not the
    # .msk sidecars.
    # ...

# Option is gone and the default (False) returns.
```

Use native Python forms (`True` and `False`) for boolean options. Rasterio will convert them GDAL's internal forms.

See the [configuration options](#) page for a complete list of available options.

5.10.2 Creation options

Each format has it's own set of driver-specific creation options that can be used to fine tune the output rasters. For details on a particular driver, see the [formats list](#).

For the purposes of this document, we will focus on the [GeoTIFF creation options](#). Some of the common GeoTIFF creation options include:

- `TILED`, `BLOCKXSIZE`, and `BLOCKYSIZE` to define the internal tiling
- `COMPRESS` to define the compression method
- `PHOTOMETRIC` to define the band's color interpretation

To specify these creation options in python code, you pass them as keyword arguments to the `rasterio.open()` command in write mode.

```
with rasterio.open("output.tif", 'w', **src.meta, compress="JPEG",
                   tiled=True, blockxsize=256, blockysize=256,
                   photometric="YCBTR") as dataset:
    # Write data to the dataset.
```

Note: The GeoTIFF format requires that `blockxsize` and `blockysize` be multiples of 16.

On the command line, `rio` commands will accept multiple `--co` options.

```
$ rio copy source.tif dest.tif --co tiled=true
```

These keyword arguments may be lowercase or uppercase, as you prefer.

Attention: Some options may at a glance appear to be boolean, but are not. The GeoTIFF format's BIGTIFF option is one of these. The value must be YES, NO, IF_NEEDED, or IF_SAFER.

Note: Some *configuration* options also have an effect on driver behavior at creation time.

5.11 Interoperability

5.11.1 Image processing software

Some python image processing software packages organize arrays differently than rasterio. The interpretation of a 3-dimension array read from rasterio is:

```
(bands, rows, columns)
```

while image processing software like `scikit-image`, `pillow` and `matplotlib` are generally ordered:

```
(rows, columns, bands)
```

The number of rows defines the dataset's height, the columns are the dataset's width.

Numpy provides a way to efficiently swap the axis order and you can use the following reshape functions to convert between raster and image axis order:

```
>>> import rasterio
>>> from rasterio.plot import reshape_as_raster, reshape_as_image

>>> raster = rasterio.open("tests/data/RGB.byte.tif").read()
>>> raster.shape
(3, 718, 791)

>>> image = reshape_as_image(raster)
>>> image.shape
(718, 791, 3)

>>> raster2 = reshape_as_raster(image)
>>> raster2.shape
(3, 718, 791)
```

5.12 Masking a raster using a shapefile

Using `rasterio` with `fiona`, it is simple to open a shapefile, read geometries, and mask out regions of a raster that are outside the polygons defined in the shapefile.


```
import fiona
import rasterio
import rasterio.mask

with fiona.open("tests/data/box.shp", "r") as shapefile:
    shapes = [feature["geometry"] for feature in shapefile]
```

This shapefile contains a single polygon, a box near the center of the raster, so in this case, our list of features is one element long.

```
with rasterio.open("tests/data/RGB.byte.tif") as src:
    out_image, out_transform = rasterio.mask.mask(src, shapes, crop=True)
    out_meta = src.meta
```

Using `plot` and `imshow` from `matplotlib`, we can see the region defined by the shapefile in red overlaid on the original raster.




Applying the features in the shapefile as a mask on the raster sets all pixels outside of the features to be zero. Since `crop=True` in this example, the extent of the raster is also set to be the extent of the features in the shapefile. We can

then use the updated spatial transform and raster height and width to write the masked raster to a new file.

```
out_meta.update({"driver": "GTiff",
                 "height": out_image.shape[1],
                 "width": out_image.shape[2],
                 "transform": out_transform})

with rasterio.open("RGB.byte.masked.tif", "w", **out_meta) as dest:
    dest.write(out_image)
```




5.13 Nodata Masks

Nodata masks allow you to identify regions of valid data values. In using Rasterio, you'll encounter two different kinds of masks.

One is the the valid data mask from GDAL, an unsigned byte array with the same number of rows and columns as the dataset in which non-zero elements (typically 255) indicate that the corresponding data elements are valid. Other elements are invalid, or *nodata* elements.

The other kind of mask is Numpy's [masked array](#) which has the inverse sense: *True* values in a masked array's mask indicate that the corresponding data elements are invalid. With care, you can safely navigate convert between the two mask types.

Consider Rasterio's RGB.byte.tif test dataset. It has 718 rows and 791 columns of pixels. Each pixel has 3 8-bit (uint8) channels or bands. It has a trapezoid of image data within a rectangular background of 0,0,0 value pixels.



Metadata in the dataset declares that values of 0 will be interpreted as invalid data or *nodata* pixels. In, e.g., merging the image with adjacent scenes, we'd like to ignore the nodata pixels and have only valid image data in our final mosaic.

Let's look at the two kinds of masks and their inverse relationship in the context of RGB.byte.tif.

```
>>> import rasterio
>>> src = rasterio.open("tests/data/RGB.byte.tif")
>>> src.shape
(718, 791)
>>> src.count
3
>>> src.dtypes
('uint8', 'uint8', 'uint8')
>>> src.nodatavals
(0.0, 0.0, 0.0)
```

(continues on next page)

(continued from previous page)

```
>>> src.nodata
0.0
```

5.13.1 Reading dataset masks


For every band of a dataset there is a mask. These masks can be had as arrays using the dataset's `read_masks()` method. Below, `msk` is the valid data mask corresponding to the first dataset band.

```
>>> msk = src.read_masks(1)
>>> msk.shape
(718, 791)
>>> msk
array([[0, 0, 0, ..., 0, 0, 0],
       [0, 0, 0, ..., 0, 0, 0],
       [0, 0, 0, ..., 0, 0, 0],
       ...
       [0, 0, 0, ..., 0, 0, 0],
       [0, 0, 0, ..., 0, 0, 0],
       [0, 0, 0, ..., 0, 0, 0]], dtype=uint8)
```

This 2D array is a valid data mask in the sense of [GDAL RFC 15](#). The `0` values in its corners represent *nodata* regions. Zooming in on the interior of the mask array shows the `255` values that indicate *valid data* regions.

```
>>> msk[200:205,200:205]
array([[255, 255, 255, 255, 255],
       [255, 255, 255, 255, 255],
       [255, 255, 255, 255, 255],
       [255, 255, 255, 255, 255],
       [255, 255, 255, 255, 255]], dtype=uint8)
```

Displayed using Matplotlib's `imshow()`, the mask looks like this:



Wait, what are these 0 values in the mask interior? This is an example of a problem inherent in 8-bit raster data: lack of dynamic range. The dataset creator has said that 0 values represent missing data (see the `nodatavals` property in the first code block of this document), but some of the valid data have values so low they've been rounded during processing to zero. This can happen in scaling 16-bit data to 8 bits. There's no magic nodata value bullet for this. Using 16 bits per band helps, but you really have to be careful with 8-bit per band datasets and their nodata values.

5.13.2 Writing masks

Writing a mask that applies to all dataset bands is just as straightforward: pass an ndarray with `True` (or values that evaluate to `True`) to indicate valid data and `False` to indicate no data to `write_mask()`. Consider a copy of the test data opened in “`r+`” (update) mode.

```
>>> import shutil
>>> import rasterio

>>> tmp = shutil.copy("tests/data/RGB.byte.tif", "/tmp/RGB.byte.tif")
>>> src = rasterio.open(tmp, mode="r+")
```

To mark that all pixels of all bands are valid (i.e., to override nodata metadata values that can't be unset), you'd do this.

```
>>> src.write_mask(True)
>>> src.read_masks(1).all()
True
```

No data have been altered, nor have the dataset's nodata values been changed. A new band has been added to the dataset to store the valid data mask. By default it is saved to a “sidecar” GeoTIFF alongside the dataset file. When such a .msk GeoTIFF exists, Rasterio will ignore the nodata metadata values and return mask arrays based on the .msk file.


```
$ ls -l copy.tif*
-rw-r--r--@ 1 sean  staff  1713704 Mar 24 14:19 copy.tif
-rw-r--r--  1 sean  staff     916 Mar 24 14:25 copy.tif.msk
```

Can Rasterio help fix buggy nodata masks like the ones in RGB.byte.tif? It certainly can. Consider a fresh copy of that file.

```
>>> src.close()
>>> tmp = shutil.copy("tests/data/RGB.byte.tif", "/tmp/RGB.byte.tif")
>>> src = rasterio.open(tmp, mode="r+")
```


This time we'll read all 3 band masks (based on the nodata values, not a .msk GeoTIFF) and show them as an RGB image (with the help of *numpy.dstack()*):

```
>>> msk = src.read_masks()
>>> show(np.dstack(msk))
```




Colored regions appear where valid data pixels don't quite coincide. This is, again, an artifact of scaling data down to 8 bits per band. We'll begin by constructing a new mask array from the logical conjunction of the three band masks we've read.

```
>>> new_msk = (msk[0] & msk[1] & msk[2])
>>> show(new_msk)
```



Now we'll use `sieve()` to shake out the small buggy regions of the mask. I've found the right value for the `size` argument empirically.

```
>>> from rasterio.features import sieve
>>> sieved_msk = sieve(new_msk, size=800)
>>> show(sieved_msk)
```



Last thing to do is write that sieved mask back to the dataset.

```
>>> src.write_mask(sieved_msk)
>>> src.close()
```

The result is a properly masked dataset that allows some 0 value pixels to be considered valid.

5.13.3 Numpy masked arrays

If you want, you can read dataset bands as numpy masked arrays.

```
>>> src = rasterio.open("tests/data/RGB.byte.tif")
>>> blue = src.read(1, masked=True)
>>> blue.mask
array([[ True,  True,  True, ...,  True,  True,  True],
       [ True,  True,  True, ...,  True,  True,  True],
       [ True,  True,  True, ...,  True,  True,  True],
       ...
       [ True,  True,  True, ...,  True,  True,  True],
       [ True,  True,  True, ...,  True,  True,  True],
       [ True,  True,  True, ...,  True,  True,  True]], dtype=bool)
```

As mentioned earlier, this mask is the inverse of the GDAL band mask. To get a mask conforming to GDAL RFC 15, do this:

```
>>> msk = (~blue.mask * 255).astype('uint8')
```

You can rely on this Rasterio identity for any integer value N.

```
>>> N = 1
>>> (~src.read(N, masked=True).mask * 255 == src.read_masks(N)).all()
True
```

5.13.4 Dataset masks

Sometimes a per-band mask is not appropriate. In this case you can either construct a mask out of the component bands (or other auxillary data) manually *or* use the Rasterio dataset's `src.dataset_mask()` function. This returns a 2D array with a GDAL-style mask determined by the following criteria, in order of precedence:

1. If a .msk file, dataset-wide alpha or internal mask exists, it will be used as the dataset mask.
2. If a 4-band RGBA with a shadow nodata value, band 4 will be used as the dataset mask.
3. If a nodata value exists, use the binary OR (`|`) of the band masks
4. If no nodata value exists, return a mask filled with all valid data (255)

Note that this differs from `read_masks` and GDAL RFC15 in that it applies per-dataset, not per-band.

5.13.5 Nodata representations in raster files

The storage and representation of nodata differs depending on the data format and configuration options. While Rasterio provides an abstraction for those details when reading, it's often important to understand the differences when creating, manipulating and writing raster data.

- **Nodata values:** the `src.nodata` value is used to define which pixels should be masked.
- **Alpha band:** with RGB imagery, an additional 4th band (containing a GDAL-style 8-bit mask) is sometimes provided to explicitly define the mask.
- **Internal mask band:** GDAL provides the ability to store an additional boolean 1-bit mask that is stored internally to the dataset. This option relies on a GDAL environment with `GDAL_TIFF_INTERNAL_MASK=True`. Otherwise the mask will be written externally.
- **External mask band:** Same as above but the mask band is stored in a sidecar `.msk` file (default).

5.14 In-Memory Files

Other sections of this documentation have explained how Rasterio can access data stored in existing files on disk written by other programs or write files to be used by other GIS programs. Filenames have been the typical inputs and files on disk have been the typical outputs.

```
with rasterio.open('example.tif') as dataset:
    data_array = dataset.read()
```

There are different options for Python programs that have streams of bytes, e.g., from a network socket, as their input or output instead of filenames. One is the use of a temporary file on disk.

```
import tempfile

with tempfile.NamedTemporaryFile() as tmpfile:
    tmpfile.write(data)
    with rasterio.open(tmpfile.name) as dataset:
        data_array = dataset.read()
```

Another is Rasterio's `MemoryFile`, an abstraction for objects in GDAL's in-memory filesystem.

5.14.1 MemoryFile: BytesIO meets NamedTemporaryFile

The `MemoryFile` class behaves a bit like `BytesIO` and `NamedTemporaryFile`. A GeoTIFF file in a sequence of data bytes can be opened in memory as shown below.

```
from rasterio.io import MemoryFile

with MemoryFile(data) as memfile:
    with memfile.open() as dataset:
        data_array = dataset.read()
```

This code can be several times faster than the code using `NamedTemporaryFile` at roughly double the price in memory.

5.14.2 Writing MemoryFiles

Incremental writes to an empty `MemoryFile` are also possible.

```
with MemoryFile() as memfile:
    while True:
        data = f.read(8192) # ``f`` is an input stream.
        if not data:
            break
        memfile.write(data)
    with memfile.open() as dataset:
        data_array = dataset.read()
```

These two modes are incompatible: a `MemoryFile` initialized with a sequence of bytes cannot be extended.

An empty `MemoryFile` can also be written to using dataset API methods.

```
with MemoryFile() as memfile:
    with memfile.open(driver='GTiff', count=3, ...) as dataset:
        dataset.write(data_array)
```

5.14.3 Reading MemoryFiles

Like BytesIO, MemoryFile implements the Python file protocol and provides `read()`, `seek()`, and `tell()` methods. Instances are thus suitable as arguments for methods like `requests.post()`.

```
with MemoryFile() as memfile:
    with memfile.open(driver='GTiff', count=3, ...) as dataset:
        dataset.write(data_array)

    requests.post('https://example.com/upload', data=memfile)
```

5.15 Migrating to Rasterio 1.0

5.15.1 affine.Affine() vs. GDAL-style geotransforms

One of the biggest API changes on the road to Rasterio 1.0 is the full deprecation of GDAL-style geotransforms in favor of the `affine` library. For reference, an `affine.Affine()` looks like:

```
affine.Affine(a, b, c,
              d, e, f)
```

and a GDAL geotransform looks like:

```
(c, a, b, f, d, e)
```

Fundamentally these two constructs provide the same information, but the `Affine()` object is more useful.

Here's a history of this feature:

1. Originally, functions with a `transform` argument expected a GDAL geotransform.
2. The introduction of the `affine` library involved creating a temporary `affine` argument for `rasterio.open()` and a `src.affine` property. Users could pass an `Affine()` to `affine` or `transform`, but a GDAL geotransform passed to `transform` would issue a deprecation warning.
3. `src.transform` remained a GDAL geotransform, but issued a warning. Users were pointed to `src.affine` during the transition phase.
4. Since the above changes, several functions have been added to Rasterio that accept a `transform` argument. Rather than add an `affine` argument to each, the `transform` argument could be either an `Affine()` object or a GDAL geotransform, the latter issuing the same deprecation warning.

The original plan was to remove the `affine` argument + property, and assume that the object passed to `transform` is an `Affine()`. However, after [further discussion](#) it was determined that since `Affine()` and GDAL geotransforms are both 6 element tuples users may experience unexplained errors and outputs, so an exception is raised instead to better highlight the error.

Before 1.0b1:

- `rasterio.open()` will still accept `affine` and `transform`, but the former now issues a deprecation warning and the latter raises an exception if it does not receive an `Affine()`.
- If `rasterio.open()` receives both `affine` and `transform` a warning is issued and `transform` is used.
- `src.affine` remains but issues a deprecation warning.
- `src.transform` returns an `Affine()`.

- All other Rasterio functions with a `transform` argument now raise an exception if they receive a GDAL geotransform.

Tickets

- #86 - Announcing the plan to switch from GDAL geotransforms to `Affine()`.
- #763 - Implementation of the migration and some further discussion.

Beginning in 1.0b1:

- In `rasterio.open` “affine” will no longer be an alias for the `transform` keyword argument.
- Dataset objects will no longer have an `affine` property.
- The `transform` keyword argument and property is always an instance of the `Affine` class.

I/O Operations

Methods related to reading band data and dataset masks have changed in 1.0.

Beginning with version 1.0b1, there is no longer a `read_mask` method, only `read_masks`. Datasets may be opened in read-write “w+” mode when their formats allow and a warning will be raised when band data or masks are read from datasets opened in “w” mode.

Beginning with 1.0.0, the “w” mode will become write-only and reading data or masks from datasets opened in “w” will be prohibited.

5.15.2 Deprecated: `rasterio.drivers()`

Previously users could register GDAL’s drivers and open a datasource with:

```
import rasterio

with rasterio.drivers():
    with rasterio.open('tests/data/RGB.byte.tif') as src:
        pass
```

but Rasterio 1.0 contains more interactions with GDAL’s environment, so `rasterio.drivers()` has been replaced with:

```
import rasterio
import rasterio.env

with rasterio.Env():
    with rasterio.open('tests/data/RGB.byte.tif') as src:
        pass
```

Tickets

- #665 - Deprecation of `rasterio.drivers()` and introduction of `rasterio.Env()`.

Removed: `src.read_band()`

The `read_band()` method has been replaced by `read()`, which allows for faster I/O and reading multiple bands into a single `numpy.ndarray()`.

For example:

```
import numpy as np
import rasterio

with rasterio.open('tests/data/RGB.byte.tif') as src:
    data = np.array(map(src.read_band, (1, 2, 3)))
    band1 = src.read_band(1)
```

is now:

```
import rasterio

with rasterio.open('tests/data/RGB.byte.tif') as src:
    data = src.read((1, 2, 3))
    band1 = src.read(1)
```

Tickets

- #83 - Introduction of `src.read()`.
- #96, #284 - Deprecation of `src.read_band()`.

Removed: `src.read_mask()`

The `src.read_mask()` method produced a single mask for the entire datasource, but could not handle producing a single mask per band, so it was deprecated in favor of `src.read_masks()`, although it has no direct replacement.

Tickets

- #284 - Deprecation of `src.read_mask()`.

5.15.3 Moved: Functions for working with dataset windows

Several functions in the top level `rasterio` namespace for working with dataset windows have been moved to `rasterio.windows.*`:

- `rasterio.get_data_window()`
- `rasterio.window_union()`
- `rasterio.window_intersection()`
- `rasterio.windows_intersect()`

Tickets

- #609 - Introduction of `rasterio.windows`.

5.15.4 Moved: `rasterio.tool`

This module has been removed completely and its contents have been moved to several different locations:

```
rasterio.tool.show()      -> rasterio.plot.show()
rasterio.tool.show_hist() -> rasterio.plot.show_hist()
rasterio.tool.stats()    -> rasterio.rio.insp.stats()
rasterio.tool.main()     -> rasterio.rio.insp.main()
```

Tickets

- #609 - Deprecation of `rasterio.tool`.

5.15.5 Moved: `rasterio.tools`

This module has been removed completely and its contents have been moved to several different locations:

```
rasterio.tools.mask.mask() -> rasterio.mask.mask()
rasterio.tools.merge.merge() -> rasterio.merge.merge()
```

Tickets

- #609 - Deprecation of `rasterio.tools`.

5.15.6 Removed: `rasterio.warp.RESAMPLING`

This enum has been replaced by `rasterio.warp.Resampling`.

5.15.7 Removed: dataset's `ul()` method

This method has been replaced by the `xy()` method.

5.15.8 Signature Changes

For both `rasterio.features.sieve()` and `rasterio.features.rasterize()` the `output` argument has been replaced with `out`. Previously the use of `output` issued a deprecation warning.

5.15.9 Deprecation of dataset property `set_*` and `get_*` methods

Methods `get_crs`, `set_crs`, `set_nodatavals`, `set_descriptions`, `set_units`, and `set_gcps` are deprecated and will be removed in version 1.0. They have been replaced by fully settable dataset properties `crs`, `nodatavals`, `descriptions`, `units`, and `gcps`.

In the cases of units and descriptions, `set_band_unit` and `set_band_description` methods remain to support the `rio-edit-info` command.

5.15.10 Creation Options

Rasterio no longer saves dataset creation options to the metadata of created datasets and will ignore such metadata starting in version 1.0. Users may opt in to this by setting `RIO_IGNORE_CREATION_KWDS=True` in their environments.

5.16 Overviews

Overviews are reduced resolution versions of your dataset that can speed up rendering when you don't need full resolution. By precomputing the upsampled pixels, rendering can be significantly faster when zoomed out.

Overviews can be stored internally or externally, depending on the file format.

In some cases we may want to make a copy of the test data to avoid altering the original.

```
>>> import shutil  
>>> path = shutil.copy('tests/data/RGB.byte.tif', '/tmp/RGB.byte.tif')
```

We must specify the zoom factors for which to build overviews. Commonly these are exponents of 2

```
>>> factors = [2, 4, 8, 16]
```

To control the visual quality of the overviews, the ‘nearest’, ‘cubic’, ‘average’, ‘mode’, and ‘gauss’ resampling algorithms are available. These are available through the `Resampling` enum

```
>>> from rasterio.enums import Resampling
```

Creating overviews requires opening a dataset in `r+` mode, which gives us access to update the data in place. By convention we also add a tag in the `rio_overview` namespace so that readers can determine what resampling method was used.

```
>>> import rasterio  
>>> dst = rasterio.open(path, 'r+')
>>> dst.build_overviews(factors, Resampling.average)
>>> dst.update_tags(ns='rio_overview', resampling='average')
>>> dst.close()
```

We can read the updated dataset and confirm that the overviews are present

```
>>> src = rasterio.open(path, 'r')
>>> [src.overviews(i) for i in src.indexes]
[[2, 4, 8, 16], [2, 4, 8, 16], [2, 4, 8, 16]]
>>> src.tags(ns='rio_overview').get('resampling')
'average'
```


And to leverage the overviews, we can perform a decimated read at a reduced resolution which should allow libgdal to read directly from the overviews rather than compute them on-the-fly.

```
>>> src.read().shape
(3, 718, 791)
>>> src.read(out_shape=(3, int(src.height / 4), int(src.width / 4))).shape
(3, 179, 197)
```

5.17 Plotting

Rasterio reads raster data into numpy arrays so plotting a single band as two dimensional data can be accomplished directly with pyplot.

```
>>> import rasterio
>>> from matplotlib import pyplot
>>> src = rasterio.open("tests/data/RGB.byte.tif")
>>> pyplot.imshow(src.read(1), cmap='pink')
<matplotlib.image.AxesImage object at 0x...>
>>> pyplot.show()
```




Rasterio also provides `rasterio.plot.show()` to perform common tasks such as displaying multi-band images as RGB and labeling the axes with geo-referenced extents.

The first argument to `show()` represent the data source to be plotted. This can be one of

- A dataset object opened in ‘r’ mode
- A single band of a source, represented by a `(src, band_index)` tuple
- A numpy ndarray, 2D or 3D. If the array is 3D, ensure that it is in rasterio band order.


Thus the following operations for 3-band RGB data are equivalent. Note that when passing arrays, you can pass in a transform in order to get extent labels.

```
>>> from rasterio.plot import show
>>> show(src)
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
>>> show(src.read(), transform=src.transform)
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
```




and similarly for single band plots. Note that you can pass in `cmap` to specify a matplotlib color ramp. Any kwargs passed to `show()` will be passed through to the underlying pyplot functions.

```
>>> show((src, 2), cmap='viridis')
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
>>> show(src.read(2), transform=src.transform, cmap='viridis')
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
```




You can create a figure with multiple subplots by passing the `show(..., ax=ax1)` argument. Also note that this example demonstrates setting the overall figure size and sets a title for each subplot.

```
>>> fig, (axr, axg, axb) = pyplot.subplots(1,3, figsize=(21,7))
>>> show((src, 1), ax=axr, cmap='Reds', title='red channel')
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
>>> show((src, 2), ax=axg, cmap='Greens', title='green channel')
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
>>> show((src, 3), ax=axb, cmap='Blues', title='blue channel')
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
>>> pyplot.show()
```




For single-band rasters, there is also an option to generate contours.

```
>>> fig, ax = pyplot.subplots(1, figsize=(12, 12))
>>> show((src, 1), cmap='Greys_r', interpolation='none', ax=ax)
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
>>> show((src, 1), contour=True, ax=ax)
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
>>> pyplot.show()
```




Rasterio also provides a `show_hist()` function for generating histograms of single or multiband rasters:

```
>>> from rasterio.plot import show_hist
>>> show_hist(
...     src, bins=50, lw=0.0, stacked=False, alpha=0.3,
...     histtype='stepfilled', title="Histogram")
```



The `show_hist()` function also takes an `ax` argument to allow subplot configurations

```
>>> fig, (axrgb, axhist) = pyplot.subplots(1, 2, figsize=(14,7))
>>> show(src, ax=axrgb)
<matplotlib.axes._subplots.AxesSubplot object at 0x...>
>>> show_hist(src, bins=50, histtype='stepfilled',
...             lw=0.0, stacked=False, alpha=0.3, ax=axhist)
>>> pyplot.show()
```



5.18 Profiles and Writing Files

How to use profiles when opening files.

Like Python's built-in `open()` function, `rasterio.open()` has two primary arguments: a path (or URL) and an optional mode ('`r`', '`w`', '`r+`', or '`w+`'). In addition there are a number of keyword arguments, several of which are required when creating a new dataset:

- driver
- width, height
- count
- dtype
- crs
- transform

These same parameters surface in a dataset's `profile` property. Exploiting the symmetry between a profile and dataset opening keyword arguments is good Rasterio usage.

```
with rasterio.open('first.jp2') as src_dataset:

    # Get a copy of the source dataset's profile. Thus our
    # destination dataset will have the same dimensions,
    # number of bands, data type, and georeferencing as the
    # source dataset.
    kwds = src_dataset.profile

    # Change the format driver for the destination dataset to
    # 'GTiff', short for GeotIFF.
    kwds['driver'] = 'GTiff'
```

(continues on next page)

(continued from previous page)

```
# Add GeoTIFF-specific keyword arguments.
kwds['tiled'] = True
kwds['blockxsize'] = 256
kwds['blockysize'] = 256
kwds['photometric'] = 'YCbCr'
kwds['compress'] = 'JPEG'

with rasterio.open('second.tif', 'w', **kwds) as dst_dataset:
    # Write data to the destination dataset.
```

The `rasterio.profiles` module contains an example of a named profile that may be useful in applications:

```
class DefaultGTiffProfile(Profile):
    """Tiled, band-interleaved, LZW-compressed, 8-bit GTiff."""

    defaults = {
        'driver': 'GTiff',
        'interleave': 'band',
        'tiled': True,
        'blockxsize': 256,
        'blockysize': 256,
        'compress': 'lzw',
        'nodata': 0,
        'dtype': uint8
    }
```

It can be used to create new datasets. Note that it doesn't count bands and that a `count` keyword argument needs to be passed when creating a profile.

```
from rasterio.profiles import DefaultGTiffProfile

with rasterio.open(
    'output.tif', 'w', **DefaultGTiffProfile(count=3)) as dst_dataset:
    # Write data to the destination dataset.
```

5.19 Reading Datasets

Todo:

- Discuss and/or link to topics

- supported formats, drivers
- vsi
- tags
- profile
- crs
- transforms
- dtypes

Dataset objects provide read, read-write, and write access to raster data files and are obtained by calling `rasterio.open()`. That function mimics Python's built-in `open()` and the dataset objects it returns mimic Python file objects.

```
>>> import rasterio
>>> src = rasterio.open('tests/data/RGB.byte.tif')
>>> src
<open DatasetReader name='tests/data/RGB.byte.tif' mode='r'>
>>> src.name
'tests/data/RGB.byte.tif'
>>> src.mode
'r'
>>> src.closed
False
```

If you try to access a nonexistent path, `rasterio.open()` does the same thing as `open()`, raising an exception immediately.


```
>>> open('/lol/wut.tif')
Traceback (most recent call last):
...
FileNotFoundError: [Errno 2] No such file or directory: '/lol/wut.tif'
>>> rasterio.open('/lol/wut.tif')
Traceback (most recent call last):
...
rasterio.errors.RasterioIOError: No such file or directory
```

Datasets generally have one or more bands (or layers). Following the GDAL convention, these are indexed starting with the number 1. The first band of a file can be read like this:

```
>>> array = src.read(1)
>>> array.shape
(718, 791)
```

The returned object is a 2-dimensional Numpy ndarray. The representation of that array at the Python prompt is a summary; the GeoTIFF file that Rasterio uses for testing has 0 values in the corners, but has nonzero values elsewhere.

```
>>> from matplotlib import pyplot
>>> pyplot.imshow(array, cmap='pink')
<matplotlib.image.AxesImage object at 0x...>
>>> pyplot.show()
```



Instead of reading single bands, all bands of the input dataset can be read into a 3-dimensional ndarray. Note that the interpretation of the 3 axes is `(bands, rows, columns)`. See [Image processing software](#) for more details on how to convert to the ordering expected by some software.

```
>>> array = src.read()  
>>> array.shape  
(3, 718, 791)
```

In order to read smaller chunks of the dataset, refer to [Windowed reading and writing](#).

The indexes, Numpy data types, and nodata values of all a dataset's bands can be had from its `indexes`, `dtypes`, and `nodatavals` attributes.

```
>>> for i, dtype, nodataval in zip(src.indexes, src.dtypes, src.nodatavals):  
...     print(i, dtype, nodataval)  
...  
1 uint8 0.0  
2 uint8 0.0  
3 uint8 0.0
```

To close a dataset, call its `close()` method.

```
>>> src.close()  
>>> src  
<closed DatasetReader name='tests/data/RGB.byte.tif' mode='r'>
```

After it's closed, data can no longer be read.

```
>>> src.read(1)
Traceback (most recent call last):
...
ValueError: can't read closed raster file
```

This is the same behavior as Python's `file`.

```
>>> f = open('README.rst')
>>> f.close()
>>> f.read()
Traceback (most recent call last):
...
ValueError: I/O operation on closed file.
```

As Python `file` objects can, Rasterio datasets can manage the entry into and exit from runtime contexts created using a `with` statement. This ensures that files are closed no matter what exceptions may be raised within the the block.

```
>>> with rasterio.open('tests/data/RGB.byte.tif', 'r') as one:
...     with rasterio.open('tests/data/RGB.byte.tif', 'r') as two:
...         print(two)
...     print(one)
...     raise Exception("an error occurred")
...
<open DatasetReader name='tests/data/RGB.byte.tif' mode='r'>
<open DatasetReader name='tests/data/RGB.byte.tif' mode='r'>
Traceback (most recent call last):
  File "<stdin>", line 5, in <module>
Exception: an error occurred
>>> print(two)
<closed DatasetReader name='tests/data/RGB.byte.tif' mode='r'>
>>> print(one)
<closed DatasetReader name='tests/data/RGB.byte.tif' mode='r'>
```

Format-specific dataset reading options may be passed as keyword arguments. For example, to turn off all types of GeoTIFF georeference except that within the TIFF file's keys and tags, pass `GEOREF_SOURCES='INTERNAL'`.

```
>>> with rasterio.open('tests/data/RGB.byte.tif', GEOREF_SOURCES='INTERNAL') as dataset:
...     # .aux.xml, .tab, .tfw sidecar files will be ignored.
```

5.20 Reprojection

Rasterio can map the pixels of a destination raster with an associated coordinate reference system and transform to the pixels of a source image with a different coordinate reference system and transform. This process is known as reprojection.

Rasterio's `rasterio.warp.reproject()` is a geospatial-specific analog to SciPy's `scipy.ndimage.interpolation.geometric_transform()`¹.

The code below reprojects between two arrays, using no pre-existing GIS datasets. `rasterio.warp.reproject()` has two positional arguments: source and destination. The remaining keyword arguments parameterize the reprojection

¹ https://docs.scipy.org/doc/scipy/reference/generated/scipy.ndimage.geometric_transform.html#scipy.ndimage.geometric_transform

transform.

```
import numpy as np
import rasterio
from rasterio import Affine as A
from rasterio.warp import reproject, Resampling

with rasterio.Env():

    # As source: a 512 x 512 raster centered on 0 degrees E and 0
    # degrees N, each pixel covering 15".
    rows, cols = src_shape = (512, 512)
    d = 1.0/240 # decimal degrees per pixel
    # The following is equivalent to
    # A(d, 0, -cols*d/2, 0, -d, rows*d/2).
    src_transform = A.translation(-cols*d/2, rows*d/2) * A.scale(d, -d)
    src_crs = {'init': 'EPSG:4326'}
    source = np.ones(src_shape, np.uint8)*255

    # Destination: a 1024 x 1024 dataset in Web Mercator (EPSG:3857)
    # with origin at 0.0, 0.0.
    dst_shape = (1024, 1024)
    dst_transform = A.translation(-237481.5, 237536.4) * A.scale(425.0, -425.0)
    dst_crs = {'init': 'EPSG:3857'}
    destination = np.zeros(dst_shape, np.uint8)

    reproject(
        source,
        destination,
        src_transform=src_transform,
        src_crs=src_crs,
        dst_transform=dst_transform,
        dst_crs=dst_crs,
        resampling=Resampling.nearest)

    # Assert that the destination is only partly filled.
    assert destination.any()
    assert not destination.all()
```

See examples/reproject.py for code that writes the destination array to a GeoTIFF file. I've uploaded the resulting file to a Mapbox map to show that the reprojection is correct: <https://a.tiles.mapbox.com/v3/sgillies.hfek2oko/page.html?secure=1#6/0.000/0.033>. (dead link)

5.20.1 Estimating optimal output shape

Rasterio provides a `rasterio.warp.calculate_default_transform()` function to determine the optimal resolution and transform for the destination raster. Given a source dataset in a known coordinate reference system, this function will return a `transform`, `width`, `height` tuple which is calculated by libgdal.

5.20.2 Reprojecting a GeoTIFF dataset

Reprojecting a GeoTIFF dataset from one coordinate reference system is a common use case. Rasterio provides a few utilities to make this even easier:

`transform_bounds()` transforms the bounding coordinates of the source raster to the target coordinate reference system, densifying points along the edges to account for non-linear transformations of the edges.

`calculate_default_transform()` transforms bounds to target coordinate system, calculates resolution if not provided, and returns destination transform and dimensions.

```
import numpy as np
import rasterio
from rasterio.warp import calculate_default_transform, reproject, Resampling

dst_crs = 'EPSG:4326'

with rasterio.open('rasterio/tests/data/RGB.byte.tif') as src:
    transform, width, height = calculate_default_transform(
        src.crs, dst_crs, src.width, src.height, *src.bounds)
    kwargs = src.meta.copy()
    kwargs.update({
        'crs': dst_crs,
        'transform': transform,
        'width': width,
        'height': height
    })

    with rasterio.open('/tmp/RGB.byte.wgs84.tif', 'w', **kwargs) as dst:
        for i in range(1, src.count + 1):
            reproject(
                source=rasterio.band(src, i),
                destination=rasterio.band(dst, i),
                src_transform=src.transform,
                src_crs=src.crs,
                dst_transform=transform,
                dst_crs=dst_crs,
                resampling=Resampling.nearest)
```

See `rasterio/rio/warp.py` for more complex examples of reprojection based on new bounds, dimensions, and resolution (as well as a command-line interface described [here](#)).

It is also possible to use `reproject()` to create an output dataset zoomed out by a factor of 2. Methods of the `rasterio.Affine` class help us generate the output dataset's transform matrix and, thereby, its spatial extent.

```
import numpy as np
import rasterio
from rasterio import Affine as A
```

(continues on next page)

(continued from previous page)

```

from rasterio.warp import reproject, Resampling

with rasterio.open('rasterio/tests/data/RGB.byte.tif') as src:
    src_transform = src.transform

    # Zoom out by a factor of 2 from the center of the source
    # dataset. The destination transform is the product of the
    # source transform, a translation down and to the right, and
    # a scaling.
    dst_transform = src_transform*A.translation(
        -src.width/2.0, -src.height/2.0)*A.scale(2.0)

    data = src.read()

    kwargs = src.meta
    kwargs['transform'] = dst_transform

    with rasterio.open('/tmp/zoomed-out.tif', 'w', **kwargs) as dst:
        for i, band in enumerate(data, 1):
            dest = np.zeros_like(band)

            reproject(
                band,
                dest,
                src_transform=src_transform,
                src_crs=src.crs,
                dst_transform=dst_transform,
                dst_crs=src.crs,
                resampling=Resampling.nearest)

            dst.write(dest, indexes=i)

```

5.20.3 Reprojecting with other georeferencing metadata

Most geospatial datasets have a geotransform which can be used to reproject a dataset from one coordinate reference system to another. Datasets may also be georeferenced by alternative metadata, namely Ground Control Points (gcps) or Rational Polynomial Coefficients (rpcs). For details on gcps and rpcs, see [Georeferencing](#). A common scenario is using gcps or rpcs to geocode (orthorectify) datasets, resampling and reorienting them to a coordinate reference system with a newly computed geotransform.

```

import numpy as np
import rasterio
from rasterio.warp import reproject
from rasterio.enums import Resampling

with rasterio.open('RGB.byte.rpc.vrt') as source:
    print(source.rpc)
    src_crs = "EPSG:4326" # This is the crs of the rpcs

```

(continues on next page)

(continued from previous page)

```

# Optional keyword arguments to be passed to GDAL transformer
# https://gdal.org/api/gdal_alg.html?highlight=gdalcreategenimgprojtransformer2#
CPPv432GDALCreateGenImgProjTransformer212GDALDatasetH12GDALDatasetHPPc
kwargs = {
    'RPC_DEM': '/path/to/dem.tif'
}

# Destination: a 1024 x 1024 dataset in Web Mercator (EPSG:3857)
destination = np.zeros((1024, 1024), dtype=np.uint8)
dst_crs = "EPSG:3857"

_, dst_transform = reproject(
    rasterio.band(source, 1),
    destination,
    rpcs=source.rpcs,
    src_crs=src_crs,
    dst_crs=dst_crs,
    resampling=Resampling.nearest,
    **kwargs
)

assert destination.any()

```

Note: When reprojecting a dataset with gcps or rpcs, the src_crs parameter should be supplied with the coordinate reference system that the gcps or rpcs are referenced against. By definition rpcs are always referenced against WGS84 ellipsoid with geographic coordinates (EPSG:4326)².

5.20.4 References

5.21 Resampling

For details on changing coordinate reference systems, see [Reprojection](#).

5.21.1 Up and downscaling

Resampling refers to changing the cell values due to changes in the raster cell grid. This can occur during reprojection. Even if the projection is not changing, we may want to change the effective cell size of an existing dataset.

Upsampling refers to cases where we are converting to higher resolution/smaller cells. *Downsampling* is resampling to lower resolution/larger cellsizes.

By reading from a raster source into an output array of a different size or by specifying an *out_shape* of a different size you are effectively resampling the data.

Here is an example of upsampling by a factor of 2 using the bilinear resampling method.

² http://geotiff.maptools.org/rpc_prop.html

```
import rasterio
from rasterio.enums import Resampling

upscale_factor = 2

with rasterio.open("example.tif") as dataset:

    # resample data to target shape
    data = dataset.read(
        out_shape=(
            dataset.count,
            int(dataset.height * upscale_factor),
            int(dataset.width * upscale_factor)
        ),
        resampling=Resampling.bilinear
    )

    # scale image transform
    transform = dataset.transform * dataset.transform.scale(
        (dataset.width / data.shape[-1]),
        (dataset.height / data.shape[-2])
    )
```

Downsampling to 1/2 of the resolution can be done with `upscale_factor = 1/2.`

5.21.2 Resampling Methods

When you change the raster cell grid, you must recalculate the pixel values. There is no “correct” way to do this as all methods involve some interpolation.

The current resampling methods can be found in the `rasterio.enums.Resampling()` class.

Of note, the default `nearest` method may not be suitable for continuous data. In those cases, `bilinear` and `cubic` are better suited. Some specialized statistical resampling methods exist, e.g. `average`, which may be useful when certain numerical properties of the data are to be retained.

5.22 Switching from GDAL’s Python bindings

This document is written specifically for users of GDAL’s Python bindings (`osgeo.gdal`) who have read about Rasterio’s [philosophy](#) and want to know what switching entails. The good news is that switching may not be complicated. This document explains the key similarities and differences between these two Python packages and highlights the features of Rasterio that can help in switching.

5.22.1 Mutual Incompatibilities

Rasterio and GDAL’s bindings can contend for global GDAL objects. Unless you have deep knowledge about both packages, choose exactly one of `import osgeo.gdal` or `import rasterio`.

GDAL’s bindings (`gdal` for the rest of this document) and Rasterio are not entirely compatible and should not, without a great deal of care, be imported and used in a single Python program. The reason is that the dynamic library they each load (these are C extension modules, remember), `libgdal.so` on Linux, `gdal.dll` on Windows, has a number of global objects and the two modules take different approaches to managing these objects.

Static linking of the GDAL library for `gdal` and `rasterio` can avoid this contention, but in practice you will almost never see distributions of these modules that statically link the GDAL library.

Beyond the issues above, the modules have different styles – `gdal` reads and writes like C while `rasterio` is more Pythonic – and don’t complement each other well.

5.22.2 The GDAL Environment

GDAL library functions are executed in a context of format drivers, error handlers, and format-specific configuration options that this document will call the “GDAL Environment.” Rasterio has an abstraction for the GDAL environment, `gdal` does not.

With `gdal`, this context is initialized upon import of the module. This makes sense because `gdal` objects are thin wrappers around functions and classes in the GDAL dynamic library that generally require registration of drivers and error handlers. The `gdal` module doesn’t have an abstraction for the environment, but it can be modified using functions like `gdal.SetErrorHandler()` and `gdal.UseExceptions()`.

Rasterio has modules that don’t require complete initialization and configuration of GDAL (`rasterio.dtypes`, `rasterio.profiles`, and `rasterio.windows`, for example) and in the interest of reducing overhead doesn’t register format drivers and error handlers until they are needed. The functions that do need fully initialized GDAL environments will ensure that they exist. `rasterio.open()` is the foremost of this category of functions. Consider the example code below.

```
import rasterio
# The GDAL environment has no registered format drivers or error
# handlers at this point.

with rasterio.open('example.tif') as src:
    # Format drivers and error handlers are registered just before
    # open() executes.
```

Importing `rasterio` does not initialize the GDAL environment. Calling `rasterio.open()` does. This is different from `gdal` where `import osgeo.gdal`, not `osgeo.gdal.Open()`, initializes the GDAL environment.

Rasterio has an abstraction for the GDAL environment, `rasterio.Env`, that can be invoked explicitly for more control over the configuration of GDAL as shown below.

```
import rasterio
# The GDAL environment has no registered format drivers or error
# handlers at this point.

with rasterio.Env(CPL_DEBUG=True, GDAL_CACHEMAX=128000000):
    # This ensures that all drivers are registered in the global
    # context. Within this block *only* GDAL's debugging messages
    # are turned on and the raster block cache size is set to 128 MB.

    with rasterio.open('example.tif') as src:
        # Perform GDAL operations in this context.
        #
        # ...
        # Done.

# At this point, configuration options are set back to their
# previous (possibly unset) values. The raster block cache size
# is returned to its default (5% of available RAM) and debugging
# messages are disabled.
```

As mentioned previously, gdal has no such abstraction for the GDAL environment. The nearest approximation would be something like the code below.

```
from osgeo import gdal

# Define a new configuration, save the previous configuration,
# and then apply the new one.
new_config = {
    'CPL_DEBUG': 'ON', 'GDAL_CACHEMAX': '512'}
prev_config = {
    key: gdal.GetConfigOption(key) for key in new_config.keys()}
for key, val in new_config.items():
    gdal.SetConfigOption(key, val)

# Perform GDAL operations in this context.
#
# ...
# Done.

# Restore previous configuration.
for key, val in prev_config.items():
    gdal.SetConfigOption(key, val)
```

Rasterio achieves this with a single Python statement.

```
with rasterio.Env(CPL_DEBUG=True, GDAL_CACHEMAX=512000000):
    # ...
```

Please note that to the Env class, GDAL_CACHEMAX is strictly an integer number of bytes. GDAL's shorthand notation is not supported.

5.22.3 Format Drivers

gdal provides objects for each of the GDAL format drivers. With Rasterio, format drivers are represented by strings and are used only as arguments to functions like `rasterio.open()`.

```
dst = rasterio.open('new.tif', 'w', format='GTiff', **kwargs)
```

Rasterio uses the same format driver names as GDAL does.

5.22.4 Dataset Identifiers

Rasterio uses URIs to identify datasets, with schemes for different protocols. The GDAL bindings have their own special syntax.

Unix-style filenames such as `/var/data/example.tif` identify dataset files for both Rasterio and gdal. Rasterio also accepts ‘file’ scheme URIs like `file:///var/data/example.tif`.

Rasterio identifies datasets within ZIP or tar archives using Apache VFS style identifiers like `zip:///var/data/example.zip!example.tif` or `tar:///var/data/example.tar!example.tif`.

Datasets served via HTTPS are identified using ‘https’ URIs like `https://landsat-pds.s3.amazonaws.com/L8/139/045/LC81390452014295LGN00/LC81390452014295LGN00_B1.TIF`.

Datasets on AWS S3 are identified using ‘s3’ scheme identifiers like `s3://landsat-pds/L8/139/045/LC81390452014295LGN00/LC81390452014295LGN00_B1.TIF`.

With gdal, the equivalent identifiers are respectively `/vsizip//var/data/example.zip/example.tif`, `/vsitar//var/data/example.tar/example.tif`, `/vsicurl/landsat-pds.s3.amazonaws.com/L8/139/045/LC81390452014295LGN00/LC81390452014295LGN00_B1.TIF`, and `/vsis3/landsat-pds/L8/139/045/LC81390452014295LGN00/LC81390452014295LGN00_B1.TIF`.

To help developers switch, Rasterio will accept these identifiers and other format-specific connection strings, too, and dispatch them to the proper format drivers and protocols.

5.22.5 Dataset Objects

Rasterio and gdal each have dataset objects. Not the same classes, of course, but not radically different ones. In each case, you generally get dataset objects through an “opener” function: `rasterio.open()` or `gdal.Open()`.

So that Python developers can spend less time reading docs, the dataset object returned by `rasterio.open()` is modeled on Python’s file object. It even has the `close()` method that gdal lacks so that you can actively close dataset connections.

5.22.6 Bands

gdal and Rasterio both have band objects. But unlike gdal’s band, Rasterio’s band is just a tuple of the dataset, band index and some other band properties. Thus Rasterio never has objects with dangling dataset pointers. With Rasterio, bands are represented by a numerical index, starting from 1 (as GDAL does), and are used as arguments to dataset methods. To read the first band of a dataset as a Numpy ndarray, do this.

```
with rasterio.open('example.tif') as src:
    band1 = src.read(1)
```

A band object can be used to represent a single band (or a sequence of bands):

```
with rasterio.open('example.tif') as src:
    bnd = rasterio.band(src, 1)
    print(bnd.dtype)
```

Other attributes of GDAL band objects generally surface in Rasterio as tuples returned by dataset attributes, with one value per band, in order.

```
>>> src = rasterio.open('example.tif')
>>> src.indexes
(1, 2, 3)
>>> src.dtypes
('uint8', 'uint8', 'uint8')
>>> src.descriptions
('Red band', 'Green band', 'Blue band')
>>> src.units
('DN', 'DN', 'DN')
```

Developers that want read-only band objects for their applications can create them by zipping these tuples together.

```
from collections import namedtuple

Band = namedtuple('Band', ['idx', 'dtype', 'description', 'units'])

src = rasterio.open('example.tif')
bands = [Band(vals) for vals in zip(
    src.indexes, src.dtypes, src.descriptions, src.units)]
```

Namedtuples are like lightweight classes.

```
>>> for band in bands:
...     print(band.idx)
...
1
2
3
```

5.22.7 Geotransforms

The `transform` attribute of a Rasterio dataset object is comparable to the `GeoTransform` attribute of a GDAL dataset, but Rasterio's has more power. It's not just an array of affine transformation matrix elements, it's an instance of an `Affine` class and has many handy methods. For example, the spatial coordinates of the upper left corner of any raster element is the product of the dataset's `transform` matrix and the `(column, row)` index of the element.

```
>>> src = rasterio.open('example.tif')
>>> src.transform * (0, 0)
(101985.0, 2826915.0)
```

The affine transformation matrix can be inverted as well.

```
>>> ~src.transform * (101985.0, 2826915.0)
(0.0, 0.0)
```

To help developers switch, `Affine` instances can be created from or converted to the sequences used by gdal.

```
>>> from rasterio.transform import Affine
>>> Affine.from_gdal(101985.0, 300.0379266750948, 0.0,
...                      2826915.0, 0.0, -300.041782729805).to_gdal()
...
(101985.0, 300.0379266750948, 0.0, 2826915.0, 0.0, -300.041782729805)
```

5.22.8 Coordinate Reference Systems

The `crs` attribute of a Rasterio dataset object is an instance of Rasterio’s CRS class and works well with `pyproj`.

```
>>> from pyproj import Proj, transform
>>> src = rasterio.open('example.tif')
>>> transform(Proj(src.crs), Proj('+init=epsg:3857'), 101985.0, 2826915.0)
(-8789636.707871985, 2938035.238323653)
```

5.22.9 Tags

GDAL metadata items are called “tags” in Rasterio. The tag set for a given GDAL metadata namespace is represented as a dict.

```
>>> src.tags()
{'AREA_OR_POINT': 'Area'}
>>> src.tags(ns='IMAGE_STRUCTURE')
{'INTERLEAVE': 'PIXEL'}
```

The semantics of the tags in GDAL’s default and `IMAGE_STRUCTURE` namespaces are described in https://gdal.org/user/raster_data_model.html. Rasterio uses several namespaces of its own: `rio_creation_kwds` and `rio_overviews`, each with their own semantics.

5.22.10 Offsets and Windows

Rasterio adds an abstraction for subsets or windows of a raster array that GDAL does not have. A window is a pair of tuples, the first of the pair being the raster row indexes at which the window starts and stops, the second being the column indexes at which the window starts and stops. Row before column, as with `ndarray` slices. Instances of `Window` are created by passing the four subset parameters used with `gdal` to the class constructor.

```
src = rasterio.open('example.tif')

xoff, yoff = 0, 0
xsize, ysize = 10, 10
subset = src.read(1, window=Window(xoff, yoff, xsize, ysize))
```

5.22.11 Valid Data Masks

Rasterio provides an array for every dataset representing its valid data mask using the same indicators as GDAL: 0 for invalid data and 255 for valid data.

```
>>> src = rasterio.open('example.tif')
>>> src.dataset_mask()
array([[0, 0, 0, ..., 0, 0, 0],
       [0, 0, 0, ..., 0, 0, 0],
       [0, 0, 0, ..., 0, 0, 0],
       ...,
       [0, 0, 0, ..., 0, 0, 0],
       [0, 0, 0, ..., 0, 0, 0],
       [0, 0, 0, ..., 0, 0, 0]], dtype=uint8)
```

Arrays for dataset bands can also be had as a Numpy `masked_array`.

```
>>> src.read(1, masked=True)
masked_array(data =
 [[---- ... , ----]
 [---- ... , ----]
 [---- ... , ----]
 ...,
 [---- ... , ----]
 [---- ... , ----]
 [---- ... , ----]],
 mask =
 [[ True  True  True ... ,  True  True  True]
 [ True  True  True ... ,  True  True  True]
 [ True  True  True ... ,  True  True  True]
 ...,
 [ True  True  True ... ,  True  True  True]
 [ True  True  True ... ,  True  True  True]
 [ True  True  True ... ,  True  True  True]],
 fill_value = 0)
```

Where the masked array's `mask` is `True`, the data is invalid and has been masked “out” in the opposite sense of GDAL's mask.

5.22.12 Errors and Exceptions

Rasterio always raises Python exceptions when an error occurs and never returns an error code or `None` to indicate an error. `gdal` takes the opposite approach, although developers can turn on exceptions by calling `gdal.UseExceptions()`.

5.23 Tagging datasets and bands

GDAL's `data model` includes collections of key, value pairs for major classes. In that model, these are "metadata", but since they don't have to be just for metadata, these key, value pairs are called "tags" in rasterio.

5.23.1 Reading tags

I'm going to use the rasterio interactive inspector in these examples below.

```
$ rio insp tests/data/RGB.byte.tif
Rasterio 1.2.0 Interactive Inspector (Python 3.7.8)
Type "src.name", "src.read(1)", or "help(src)" for more information.
>>>
```

Tags belong to namespaces. To get a copy of a dataset's tags from the default namespace, call `tags()` with no arguments.

```
>>> import rasterio
>>> src = rasterio.open("tests/data/RGB.byte.tif")
>>> src.tags()
{'AREA_OR_POINT': 'Area'}
```

A dataset's bands may have tags, too. Here are the tags from the default namespace for the first band, accessed using the positional band index argument of `tags()`.

```
>>> src.tags(1)['STATISTICS_MEAN']
'29.947726688477'
```

These are the tags that came with the sample data I'm using to test rasterio. In practice, maintaining stats in the tags can be unreliable as there is no automatic update of the tags when the band's image data changes.

The 3 standard, non-default GDAL tag namespaces are 'SUBDATASETS', 'IMAGE_STRUCTURE', and 'RPC'. You can get the tags from these namespaces using the `ns` keyword of `tags()`.

```
>>> src.tags(ns='IMAGE_STRUCTURE')
{'INTERLEAVE': 'PIXEL'}
>>> src.tags(ns='SUBDATASETS')
{}
>>> src.tags(ns='RPC')
{}
```

A special case for GDAL tag namespaces are those prefixed with 'xml' e.g. 'xml:TRE' or 'xml:VRT'. GDAL will treat these namespaces as a single xml string.

5.23.2 Writing tags

You can add new tags to a dataset or band, in the default or another namespace, using the `update_tags()` method. Unicode tag values, too, at least for TIFF files.

```
import rasterio

with rasterio.open(
    '/tmp/test.tif',
    'w',
    driver='GTiff',
    count=1,
    dtype=rasterio.uint8,
    width=10,
    height=10) as dst:

    dst.update_tags(a='1', b='2')
    dst.update_tags(1, c=3)
    with pytest.raises(ValueError):
        dst.update_tags(4, d=4)

    # True
    assert dst.tags() == {'a': '1', 'b': '2'}
    # True
    assert dst.tags(1) == {'c': '3' }

    dst.update_tags(ns='rasterio_testing', rus=u' ')
    # True
    assert dst.tags(ns='rasterio_testing') == {'rus': u' '}
```

As with image data, tags aren't written to the file on disk until the dataset is closed.

5.24 Transforms

Rasterio supports three primary methods for transforming of coordinates from image pixel (row, col) to and from geographic/projected (x, y) coordinates. The interface for performing these coordinate transformations is available in `rasterio.transforms` through one of `AffineTransform`, `GCPTransformer`, or `RPCTransformer`. The methods `xy` and `rowcol` are responsible for converting between (row, col) -> (x, y) and (x, y) -> (row, col), respectively.

5.24.1 Using Affine transformation matrix

`rasterio.transform.AffineTransform` takes care of coordinate transformations given an Affine transformation matrix. For example

```
>>> transform = Affine(300.0379266750948, 0.0, 101985.0, 0.0,
                      -300.041782729805, 2826915.0)
>>> transformer = rasterio.transform.AffineTransform(transform)
>>> transformer.xy(0, 0)
(102135.01896333754, 2826764.979108635)
>>> transformer.rowcol(102135.01896333754, 2826764.979108635)
(0, 0)
```

This is approximately equivalent to

```
>>> transform = Affine(300.0379266750948, 0.0, 101985.0, 0.0,
                      -300.041782729805, 2826915.0)
>>> transform * (0.5, 0.5)
(102135.01896333754, 2826764.979108635)
>>> ~transform * (102135.01896333754, 2826764.979108635)
(0.5, 0.5)
```

The dataset methods `xy` and `index` use `rasterio.transform` under the hood

```
>>> with rasterio.open('RGB.byte.tif') as src:
    print(src.xy(0, 0))
(102135.01896333754, 2826764.979108635)
```

5.24.2 Using Ground Control Points

```
>>> gcps = [GroundControlPoint(row=11521.5, col=0.5, x=-123.6185142817931, y=48.
                                99561141948625, z=89.13533782958984, id='217', info=''),
            GroundControlPoint(row=11521.5, col=7448.5, x=-122.8802747777599, y=48.
                                91210259315549, z=89.13533782958984, id='234', info=''),
            GroundControlPoint(row=0.5, col=0.5, x=-123.4809665720148, y=49.
                                52809729106944, z=89.13533782958984, id='1', info=''),
            GroundControlPoint(row=0.5, col=7448.5, x=-122.7345733674704, y=49.
                                44455878004666, z=89.13533782958984, id='18', info='')]
>>> transformer = rasterio.transform.GCPTransformer(gcps)
>>> transformer.xy(0, 0)
(-123.478928146887, 49.52808986989645)
```

5.24.3 Using Rational Polynomial Coefficients

For accuracy a height value is typically required when using `RPCTransformer`. By default, a value of 0 is assumed.

```
>>> with rasterio.open('RGB.byte.rpc.vrt') as src:
    transformer = rasterio.transform.RPCTransformer(src.rpcs)
    transformer.xy(0, 0)
(-123.47959047080701, 49.52794990575094)
```

A first order correction would be to use a mean elevation value for the image

```
>>> with rasterio.open('RGB.byte.rpc.vrt') as src:
    transformer = rasterio.transform.RPCTransformer(src.rpcs)
    transformer.xy(0, 0, zs=src.rpcs.height_off)
(-123.48096552376548, 49.528097381526386)
```

Better yet is to sample height values from a digital elevation model (DEM). `RPCTransformer` allows for options to be passed to `GDALCreateRPCTransformer`

```
>>> with rasterio.open('RGB.byte.rpc.vrt') as src:
    transformer = rasterio.transform.RPCTransformer(src.rpcs, rpc_dem='vancouver-dem.
                                tif')
```

(continues on next page)

(continued from previous page)

```
transformer.xy(0, 0)
(-123.47954729595642, 49.5279448909449)
```

See https://gdal.org/api/gdal_alg.html?highlight=gdalcreaterpctransformer#_CPPv426GDALCreateRPCTransformerV2PK13GDALRP for more details.

5.24.4 Transformer Resources

The `AffineTransformer` is a pure Python class, however `GCPTransformer` and `RPCTransformer` make use of C/C++ GDAL objects. Explicit control of the transformer object can be achieved by use within a context manager or by calling `close()` method e.g.

```
>>> with rasterio.transform.RPCTransformer(rpcs) as transform:
    transform.xy(0, 0)
>>> transform.xy(0, 0)
ValueError: Unexpected NULL transformer
```

Note: If `RPC_DEM` is specified in `rpc_options`, GDAL will maintain an open file handle to the DEM until the transformer is closed.

5.25 Virtual Warping

Rasterio has a `WarpedVRT` class that abstracts many of the details of raster warping by using an in-memory `WarpedVRT`. A `WarpedVRT` can be the easiest solution for tiling large datasets.

For example, to virtually warp the `RGB.byte.tif` test dataset from its proper EPSG:32618 coordinate reference system to EPSG:3857 (Web Mercator) and extract pixels corresponding to its central zoom 9 tile, do the following.

```
from affine import Affine
import mercantile

import rasterio
from rasterio.enums import Resampling
from rasterio.vrt import WarpedVRT

with rasterio.open('tests/data/RGB.byte.tif') as src:
    with WarpedVRT(src, crs='EPSG:3857',
                    resampling=Resampling.bilinear) as vrt:

        # Determine the destination tile and its mercator bounds using
        # functions from the mercantile module.
        dst_tile = mercantile.tile(*vrt.lnglat(), 9)
        left, bottom, right, top = mercantile.xy_bounds(*dst_tile)

        # Determine the window to use in reading from the dataset.
        dst_window = vrt.window(left, bottom, right, top)

        # Read into a 3 x 512 x 512 array. Our output tile will be
```

(continues on next page)

(continued from previous page)

```

# 512 wide x 512 tall.
data = vrt.read(window=dst_window, out_shape=(3, 512, 512))

# Use the source's profile as a template for our output file.
profile = vrt.profile
profile['width'] = 512
profile['height'] = 512
profile['driver'] = 'GTiff'

# We need determine the appropriate affine transformation matrix
# for the dataset read window and then scale it by the dimensions
# of the output array.
dst_transform = vrt.window_transform(dst_window)
scaling = Affine.scale(dst_window.height / 512,
                      dst_window.width / 512)
dst_transform *= scaling
profile['transform'] = dst_transform

# Write the image tile to disk.
with rasterio.open('/tmp/test-tile.tif', 'w', **profile) as dst:
    dst.write(data)

```

5.25.1 Normalizing Data to a Consistent Grid

A WarpedVRT can be used to normalize a stack of images with differing projections, bounds, cell sizes, or dimensions against a regular grid in a defined bounding box.

The `tests/data/RGB.byte.tif` file is in UTM zone 18, so another file in a different CRS is required for demonstration. This command will create a new image with drastically different dimensions and cell size, and reproject to WGS84. As of this writing `rio warp` implements only a subset of `gdalwarp`'s features, so `gdalwarp` must be used to achieve the desired transform:

```
$ gdalwarp \
-t_srs EPSG:4326 \
-te_srs EPSG:32618 \
-te 101985 2673031 339315 2801254 \
-ts 200 250 \
tests/data/RGB.byte.tif \
tests/data/WGS84-RGB.byte.tif
```

So, the attributes of these two images drastically differ:

```
$ rio info --shape tests/data/RGB.byte.tif
718 791
$ rio info --shape tests/data/WGS84-RGB.byte.tif
250 200
$ rio info --crs tests/data/RGB.byte.tif
EPSG:32618
$ rio info --crs tests/data/WGS84-RGB.byte.tif
EPSG:4326
$ rio bounds --bbox --geographic --precision 7 tests/data/RGB.byte.tif
[-78.95865, 23.5649912, -76.5749237, 25.5508738]
```

(continues on next page)

(continued from previous page)

```
$ rio bounds --bbox --geographic --precision 7 tests/data/WGS84-RGB.byte.tif
[-78.9147773, 24.119606, -76.5963819, 25.3192311]
```

and this snippet demonstrates how to normalize data to consistent dimensions, CRS, and cell size within a pre-defined bounding box:

```
from __future__ import division

import os

import affine

import rasterio
from rasterio.crs import CRS
from rasterio.enums import Resampling
from rasterio import shutil as rio_shutil
from rasterio.vrt import WarpedVRT

input_files = (
    # This file is in EPSG:32618
    'tests/data/RGB.byte.tif',
    # This file is in EPSG:4326
    'tests/data/WGS84-RGB.byte.tif'
)

# Destination CRS is Web Mercator
dst_crs = CRS.from_epsg(3857)

# These coordinates are in Web Mercator
dst_bounds = -8744355, 2768114, -8559167, 2908677

# Output image dimensions
dst_height = dst_width = 100

# Output image transform
left, bottom, right, top = dst_bounds
xres = (right - left) / dst_width
yres = (top - bottom) / dst_height
dst_transform = affine.Affine(xres, 0.0, left,
                             0.0, -yres, top)

vrt_options = {
    'resampling': Resampling.cubic,
    'crs': dst_crs,
    'transform': dst_transform,
    'height': dst_height,
    'width': dst_width,
}

for path in input_files:
```

(continues on next page)

(continued from previous page)

```
with rasterio.open(path) as src:

    with WarpedVRT(src, **vrt_options) as vrt:

        # At this point 'vrt' is a full dataset with dimensions,
        # CRS, and spatial extent matching 'vrt_options'.

        # Read all data into memory.
        data = vrt.read()

        # Process the dataset in chunks. Likely not very efficient.
        for _, window in vrt.block_windows():
            data = vrt.read(window=window)

        # Dump the aligned data into a new file. A VRT representing
        # this transformation can also be produced by switching
        # to the VRT driver.
        directory, name = os.path.split(path)
        outfile = os.path.join(directory, 'aligned-{}.format(name))')
        rio_shutil.copy(vrt, outfile, driver='GTiff')
```

5.26 Virtual Filesystems

Rasterio uses GDAL's [virtual filesystem interface](#) to access datasets on the web, in cloud storage, in archive files, and in Python objects. Rasterio maps familiar URI schemes to GDAL virtual filesystem handlers. For example, the `https` URI scheme maps to GDAL's `/vsicurl/`. The `file` URI scheme maps to GDAL's ordinary filesystem handler and is the default for dataset URIs that have no other scheme.

To access a dataset in a local ZIP file like the one in Rasterio's test suite, prepend `zip` to the URI of the local file and add the interior path to the dataset after a `!` character. For example:

```
with rasterio.open("zip+file://tests/data/files.zip!RGB.byte.tif") as src:
    print(src.shape)

# Printed:
# (718, 791)
```

Or use `zip` as shorthand for `zip+file`.

```
with rasterio.open("zip://tests/data/files.zip!RGB.byte.tif") as src:
    print(src.shape)

# Printed:
# (718, 791)
```

Similarly, datasets in ZIP files served on the web can be accessed by using `zip+https`.

```
with rasterio.open("zip+https://github.com/rasterio/rasterio/files/13675561/files.zip!
->RGB.byte.tif") as src:
    print(src.shape)
```

(continues on next page)

(continued from previous page)

```
# Printed:  
# (718, 791)
```

Tar and gzip archives can be accessed in the same manner by prepending with `tar` or `gz` instead of `zip`.

For compatibility with legacy systems and workflows or very niche use cases, Rasterio can also use GDAL's VSI filenames.

```
with rasterio.open("/vsizip/vsicurl/https://github.com/rasterio/rasterio/files/13675561/  
files.zip/RGB.byte.tif") as src:  
    print(src.shape)  
  
# Printed:  
# (718, 791)
```

The prefixes on which GDAL filesystem handlers are registered are considered by Rasterio to be an implementation detail. You shouldn't need to think about them when using Rasterio. Use familiar and standard URIs instead, like elsewhere on the internet.

```
with rasterio.open("https://github.com/rasterio/rasterio/raw/main/tests/data/RGB.byte.tif  
") as src:  
    print(src.shape)  
  
# Printed:  
# (718, 791)
```

5.26.1 AWS S3

Note: Requires GDAL 2.1.0

This is an extra feature that must be installed by executing

```
pip install rasterio[s3]
```

After you have configured your AWS credentials as explained in the [boto3 guide](#) you can read metadata and imagery from TIFFs stored as S3 objects with no change to your code.

```
with rasterio.open("s3://landsat-pds/L8/139/045/LC81390452014295LGN00/  
LC81390452014295LGN00_B1.TIF") as src:  
    print(src.profile)  
  
# Printed:  
# {'blockxsize': 512,  
# 'blockysize': 512,  
# 'compress': 'deflate',  
# 'count': 1,  
# 'crs': {'init': u'epsg:32645'},  
# 'driver': u'GTiff',  
# 'dtype': 'uint16',  
# 'height': 7791,
```

(continues on next page)

(continued from previous page)

```
# 'interleave': 'band',
# 'nodata': None,
# 'tiled': True,
# 'transform': Affine(30.0, 0.0, 381885.0,
#                     0.0, -30.0, 2512815.0),
# 'width': 7621}
```

Note: AWS pricing concerns While this feature can reduce latency by reading fewer bytes from S3 compared to downloading the entire TIFF and opening locally, it does make at least 3 GET requests to fetch a TIFF's *profile* as shown above and likely many more to fetch all the imagery from the TIFF. Consult the AWS S3 pricing guidelines before deciding if *aws.Session* is for you.

5.27 Windowed reading and writing

Beginning in rasterio 0.3, you can read and write “windows” of raster files. This feature allows you to work on rasters that are larger than your computers RAM or process chunks of large rasters in parallel.

5.27.1 Windows

A window is a view onto a rectangular subset of a raster dataset and is described in rasterio by column and row offsets and width and height in pixels. These may be ints or floats.

```
from rasterio.windows import Window

Window(col_off, row_off, width, height)
```

Windows may also be constructed from numpy array index tuples or slice objects. Only int values are permitted in these cases.

```
Window.from_slices((row_start, row_stop), (col_start, col_stop))
Window.from_slices(slice(row_start, row_stop), slice(col_start, col_stop))
```

If height and width keyword arguments are passed to `from_slices`, relative and open-ended slices may be used.

```
Window.from_slices(slice(None), slice(None), height=100, width=100)
# Window(col_off=0.0, row_off=0.0, width=100.0, height=100.0)

Window.from_slices(slice(10, -10), slice(10, -10), height=100, width=100)
# Window(col_off=10, row_off=10, width=80, height=80)
```

5.27.2 Reading

Here is an example of reading a 256 row x 512 column subset of the rasterio test file.

```
>>> import rasterio
>>> with rasterio.open('tests/data/RGB.byte.tif') as src:
...     w = src.read(1, window=Window(0, 0, 512, 256))
...
>>> print(w.shape)
(256, 512)
```

Attention: In getting data to fill a window Rasterio will read the entirety of one or more chunks of data from the dataset. If you're reading from a GeoTIFF with 512 x 512 pixel chunks (blocks), that determines the minimum number of bytes that will be read from disk or copied over your network, even if your read window is only 1 x 1 pixels. In the case that your source dataset does not use chunks (rare, but possible) Rasterio will read the entire dataset in order to fill even a 1 x 1 pixel window. In practice, it's important to chunk the data you create and store for your applications.

5.27.3 Writing

Writing works similarly. The following creates a blank 500 column x 300 row GeoTIFF and plops 37,500 pixels with value 127 into a window 30 pixels down from and 50 pixels to the right of the upper left corner of the GeoTIFF.

```
image = numpy.ones((150, 250), dtype=rasterio.ubyte) * 127

with rasterio.open(
    '/tmp/example.tif', 'w',
    driver='GTiff', width=500, height=300, count=1,
    dtype=image.dtype) as dst:
    dst.write(image, window=Window(50, 30, 250, 150), indexes=1)
```

The result:



5.27.4 Decimation


If the write window is smaller than the data, the data will be decimated. Below, the window is scaled to one third of the source image.

```
with rasterio.open('tests/data/RGB.byte.tif') as src:
    b, g, r = (src.read(k) for k in (1, 2, 3))
    # src.height = 718, src.width = 791

write_window = Window.from_slices((30, 269), (50, 313))
# write_window.height = 239, write_window.width = 263

with rasterio.open(
        '/tmp/example.tif', 'w',
        driver='GTiff', width=500, height=300, count=3,
        dtype=r.dtype) as dst:
    for k, arr in [(1, b), (2, g), (3, r)]:
        dst.write(arr, indexes=k, window=write_window)
```

And the result:



5.27.5 Data windows

Sometimes it is desirable to crop off an outer boundary of NODATA values around a dataset:

```
from rasterio.windows import get_data_window

with rasterio.open('tests/data/RGB.byte.tif') as src:
    window = get_data_window(src.read(1, masked=True))
    # window = Window(col_off=13, row_off=3, width=757, height=711)

    kwargs = src.meta.copy()
    kwargs.update({
```

(continues on next page)

(continued from previous page)

```
'height': window.height,
'width': window.width,
'transform': rasterio.windows.transform(window, src.transform)})

with rasterio.open('/tmp/cropped.tif', 'w', **kwargs) as dst:
    dst.write(src.read(window=window))
```

5.27.6 Window transforms

The affine transform of a window can be accessed using a dataset's `window_transform` method:

```
>>> import rasterio
>>> from rasterio.windows import Window
>>> win = Window(256, 256, 128, 128)
>>> with rasterio.open('tests/data/RGB.byte.tif') as src:
...     src_transform = src.transform
...     win_transform = src.window_transform(win)
...
>>> print(src_transform)
| 300.04, 0.00, 101985.00|
| 0.00,-300.04, 2826915.00|
| 0.00, 0.00, 1.00|
>>> print(win_transform)
| 300.04, 0.00, 178794.71|
| 0.00,-300.04, 2750104.30|
| 0.00, 0.00, 1.00|
```

5.27.7 Window utilities

Basic union and intersection operations are available for windows, to streamline operations across dynamically created windows for a series of bands or datasets with the same full extent.

```
>>> from rasterio import windows
>>> # Full window is ((0, 1000), (0, 500))
>>> window1 = Window(10, 100, 490, 400)
>>> window2 = Window(50, 10, 200, 140)
>>> windows.union(window1, window2)
Window(col_off=10, row_off=10, width=490, height=490)
>>> windows.intersection(window1, window2)
Window(col_off=50, row_off=100, width=200, height=50)
```

5.27.8 Blocks

Raster datasets are generally composed of multiple blocks of data and windowed reads and writes are most efficient when the windows match the dataset's own block structure. When a file is opened to read, the shape of blocks for any band can be had from the `block_shapes` property.

```
>>> with rasterio.open('tests/data/RGB.byte.tif') as src:
...     for i, shape in enumerate(src.block_shapes, 1):
...         print((i, shape))
...
(1, (3, 791))
(2, (3, 791))
(3, (3, 791))
```

The block windows themselves can be had from the `block_windows` function.

```
>>> with rasterio.open('tests/data/RGB.byte.tif') as src:
...     for ji, window in src.block_windows(1):
...         print((ji, window))
...
((0, 0), ((0, 3), (0, 791)))
((1, 0), ((3, 6), (0, 791)))
...
```

This function returns an iterator that yields a pair of values. The second is a window tuple that can be used in calls to `read` or `write`. The first is the pair of row and column indexes of this block within all blocks of the dataset.

You may read windows of data from a file block-by-block like this.

```
>>> with rasterio.open('tests/data/RGB.byte.tif') as src:
...     for ji, window in src.block_windows(1):
...         r = src.read(1, window=window)
...         print(r.shape)
...         break
...
(3, 791)
```

Well-bred files have identically blocked bands, but GDAL allows otherwise and it's a good idea to test this assumption in your code.

```
>>> with rasterio.open('tests/data/RGB.byte.tif') as src:
...     assert len(set(src.block_shapes)) == 1
...     for ji, window in src.block_windows(1):
...         b, g, r = (src.read(k, window=window) for k in (1, 2, 3))
...         print((ji, r.shape, g.shape, b.shape))
...         break
...
((0, 0), (3, 791), (3, 791), (3, 791))
```

The `block_shapes` property is a band-ordered list of block shapes and `set(src.block_shapes)` gives you the set of unique shapes. Asserting that there is only one item in the set is effectively the same as asserting that all bands have the same block structure. If they do, you can use the same windows for each.

5.28 Writing Datasets

Todo:

- appending to existing data
 - context manager
 - write 3d vs write 2d
 - document issues with writing compressed files (per #77)
 - **discuss and refer to topics**
 - creation options
 - transforms
 - dtypes
 - block windows
-

Opening a file in writing mode is a little more complicated than opening a text file in Python. The dimensions of the raster dataset, the data types, and the specific format must be specified.

Here's an example of basic rasterio functionality. An array is written to a new single band TIFF.

```
# Register GDAL format drivers and configuration options with a
# context manager.
with rasterio.Env():

    # Write an array as a raster band to a new 8-bit file. For
    # the new file's profile, we start with the profile of the source
    profile = src.profile

    # And then change the band count to 1, set the
    # dtype to uint8, and specify LZW compression.
    profile.update(
        dtype=rasterio.uint8,
        count=1,
        compress='lzw')

    with rasterio.open('example.tif', 'w', **profile) as dst:
        dst.write(array.astype(rasterio.uint8), 1)

# At the end of the ``with rasterio.Env()`` block, context
# manager exits and all drivers are de-registered.
```

Writing data mostly works as with a Python file. There are a few format- specific differences.

5.28.1 Supported Drivers

`GTiff` is the only driver that supports writing directly to disk. `GeoTiff`s use the `RasterUpdater` and leverage the full capabilities of the `GDALCreate` function. We highly recommend using `GeoTiff` driver for writing as it is the best-tested and best-supported format.

Some other formats that are writable by GDAL can also be written by Rasterio. These use an `IndirectRasterUpdater` which does not create directly but uses a temporary in-memory dataset and `GDALCreateCopy` to produce the final output.

Some formats are known to produce invalid results using the `IndirectRasterUpdater`. These formats will raise a `RasterioIOError` if you attempt to write to the. Currently this applies to the `netCDF` driver but please let us know if you experience problems writing other formats.

PYTHON API REFERENCE

6.1 rasterio package

6.1.1 Subpackages

[rasterio.rio package](#)

Submodules

[rasterio.rio.blocks module](#)

\$ rio blocks

[rasterio.rio.bounds module](#)

[rasterio.rio.calc module](#)

\$ rio calc

[rasterio.rio.clip module](#)

File translation command

[rasterio.rio.convert module](#)

File translation command

rasterio.rio.edit_info module

Fetch and edit raster dataset metadata from the command line.

`rasterio.rio.edit_info.all_handler(ctx, param, value)`

Get tags from a template file or command line.

`rasterio.rio.edit_info.colorinterp_handler(ctx, param, value)`

Validate a string like red,green,blue,alpha and convert to a tuple. Also handle RGB and RGBA.

`rasterio.rio.edit_info.crs_handler(ctx, param, value)`

Get crs value from a template file or command line.

`rasterio.rio.edit_info.tags_handler(ctx, param, value)`

Get tags from a template file or command line.

`rasterio.rio.edit_info.transform_handler(ctx, param, value)`

Get transform value from a template file or command line.

rasterio.rio.env module

Fetch and edit raster dataset metadata from the command line.

rasterio.rio.gcps module

Command access to dataset metadata, stats, and more.

rasterio.rio.helpers module

Helper objects used by multiple CLI commands.

`rasterio.rio.helpers.coords(obj)`

Yield all coordinate coordinate tuples from a geometry or feature. From python-geojson package.

`rasterio.rio.helpers.resolve_inout(input=None, output=None, files=None, overwrite=False, num_inputs=None)`

Resolves inputs and outputs from standard args and options.

Parameters

- `input` (`str`) – A single input filename, optional.
- `output` (`str`) – A single output filename, optional.
- `files` (`str`) – A sequence of filenames in which the last is the output filename.
- `overwrite` (`bool`) – Whether to force overwriting the output file.
- `num_inputs` (`int`) – Raise exceptions if the number of resolved input files is higher or lower than this number.

Returns

- `tuple (str, list of str)` – The resolved output filename and input filenames as a tuple of length 2.
 - *If provided, the output file may be overwritten. An output*

- file extracted from files will not be overwritten unless
- overwrite is True.

Raises**click.BadParameter** –**rasterio.rio.helpers.to_lower(ctx, param, value)**

Click callback, converts values to lowercase.

rasterio.rio.helpers.write_features(fobj, collection, sequence=False, geojson_type='feature', use_rs=False, **dump_kwds)

Read an iterator of (feat, bbox) pairs and write to file using the selected modes.

rasterio.rio.info module

Command access to dataset metadata, stats, and more.

rasterio.rio.insp module

Fetch and edit raster dataset metadata from the command line.

class rasterio.rio.insp.Stats(min, max, mean)Bases: **tuple****max**

Alias for field number 1

mean

Alias for field number 2

min

Alias for field number 0

rasterio.rio.insp.main(banner, dataset, alt_interpreter=None)

Main entry point for use with python interpreter.

rasterio.rio.insp.stats(dataset)

Return a tuple with raster min, max, and mean.

rasterio.rio.main module

Main command group for Rasterio's CLI.

Subcommands developed as a part of the Rasterio package have their own modules under **rasterio.rio** (like **rasterio/rio/info.py**) and are registered in the '**rasterio.rio_commands**' entry point group in Rasterio's **setup.py**:

```
entry_points=""
[console_scripts] rio=rasterio.rio.main:main_group
[rasterio.rio_commands] bounds=rasterio.rio.bounds:bounds calc=rasterio.rio.calc:calc ...
```

Users may create their own `rio` subcommands by writing modules that register entry points in Rasterio’s ‘rasterio.rio_plugins’ group. See for example <https://github.com/sgillies/rio-plugin-example>, which has been published to PyPI as `rio-metasay`.

There’s no advantage to making a `rio` subcommand which doesn’t import rasterio. But if you are using rasterio, you may profit from Rasterio’s CLI infrastructure and the network of existing commands. Please add yours to the registry

<https://github.com/rasterio/rasterio/wiki/Rio-plugin-registry>

so that other `rio` users may find it.

`rasterio.rio.main.configure_logging(verbosity)`

`rasterio.rio.main.gdal_version_cb(ctx, param, value)`

`rasterio.rio.main.show_versions_cb(ctx, param, value)`

rasterio.rio.mask module

rasterio.rio.merge module

\$ rio merge

`rasterio.rio.merge.deprecated_precision(*args)`

rasterio.rio.options module

Registry of common `rio` CLI options. See `cligj` for more options.

```
-a, --all: Use all pixels touched by features. In rio-mask, rio-rasterize
--as-mask/--not-as-mask: interpret band as mask or not. In rio-shapes
--band/--mask: use band or mask. In rio-shapes
--bbox:
-b, --bidx: band index(es) (singular or multiple value versions).
    In rio-info, rio-sample, rio-shapes, rio-stack (different usages)
--bounds: bounds in world coordinates.
    In rio-info, rio-rasterize (different usages)
--count: count of bands. In rio-info
--crop: Crop raster to extent of features. In rio-mask
--crs: CRS of input raster. In rio-info
--default-value: default for rasterized pixels. In rio-rasterize
--dimensions: Output width, height. In rio-rasterize
--dst-crs: destination CRS. In rio-transform
--fill: fill value for pixels not covered by features. In rio-rasterize
--formats: list available formats. In rio-info
--height: height of raster. In rio-info
-i, --invert: Invert mask created from features: In rio-mask
-j, --geojson-mask: GeoJSON for masking raster. In rio-mask
--lglat: geographpic coordinates of center of raster. In rio-info
--masked/--not-masked: read masked data from source file.
    In rio-calc, rio-info
-m, --mode: output file mode (r, r+). In rio-insp
--name: input file name alias. In rio-calc
--nodata: nodata value. In rio-info, rio-merge (different usages)
```

(continues on next page)

(continued from previous page)

```
--photometric: photometric interpretation. In rio-stack
--property: GeoJSON property to use as values for rasterize. In rio-rasterize
-r, --res: output resolution.
    In rio-info, rio-rasterize (different usages. TODO: try to combine
    usages, prefer rio-rasterize version)
--sampling: Inverse of sampling fraction. In rio-shapes
--shape: shape (width, height) of band. In rio-info
--src-crs: source CRS.
    In rio-insp, rio-rasterize (different usages. TODO: consolidate usages)
--stats: print raster stats. In rio-inf
-t, --dtype: data type. In rio-calc, rio-info (different usages)
--width: width of raster. In rio-info
--with-nodata/--without-nodata: include nodata regions or not. In rio-shapes.
-v, --tell-me-more, --verbose
--vfs: virtual file system.
```

rasterio.rio.options.abspath_forward_slashes(path)

Return forward-slashed version of os.path.abspath

rasterio.rio.options.bounds_handler(ctx, param, value)

Handle different forms of bounds.

rasterio.rio.options.edit_nodata_handler(ctx, param, value)

Get nodata value from a template file or command line.

Expected values are ‘like’, ‘null’, a numeric value, ‘nan’, or None.

Return type

`float` or `None`

Raises

`click.BadParameter` –

rasterio.rio.options.file_in_handler(ctx, param, value)

Normalize ordinary filesystem and VFS paths

rasterio.rio.options.files_in_handler(ctx, param, value)

Process and validate input file names

rasterio.rio.options.files_inout_handler(ctx, param, value)

Process and validate input file names

rasterio.rio.options.from_like_context(ctx, param, value)

Return the value for an option from the context if the option or `-all` is given, else return `None`.

rasterio.rio.options.like_handler(ctx, param, value)

Copy a dataset’s meta property to the command context for access from other callbacks.

rasterio.rio.options.nodata_handler(ctx, param, value)

Return a float or `None`

rasterio.rio.overview module

Manage overviews of a dataset.

`rasterio.rio.overview.build_handler(ctx, param, value)`

`rasterio.rio.overview.get_maximum_overview_level(width, height, minsize=256)`

Calculate the maximum overview level of a dataset at which the smallest overview is smaller than *minsize*.

`rasterio.rio.overview.width`

Width of the dataset.

Type

`int`

`rasterio.rio.overview.height`

Height of the dataset.

Type

`int`

`rasterio.rio.overview.minsize`

Minimum overview size.

Type

`int` (default: 256)

Returns

`overview_level` – overview level.

Return type

`int`

rasterio.rio.rasterize module

\$ rio rasterize

`rasterio.rio.rasterize.files_handler(ctx, param, value)`

Process and validate input file names

rasterio.rio.rm module

\$ rio rm

rasterio.rio.sample module

rasterio.rio.shapes module

\$ rio shapes

`rasterio.rio.shapes.feature_gen(src, env, *args, **kwargs)`

rasterio.rio.stack module

```
$ rio stack
```

rasterio.rio.transform module

Fetch and edit raster dataset metadata from the command line.

rasterio.rio.warp module

```
$ rio warp
```

Module contents

Rasterio commandline interface components

6.1.2 Submodules

rasterio.control module

Ground control points

```
class rasterio.control.GroundControlPoint(row=None, col=None, x=None, y=None, z=None, id=None, info=None)
```

Bases: `object`

A mapping of row, col image coordinates to x, y, z.

`asdict()`

A dict representation of the GCP

rasterio.coords module

Bounding box tuple, and disjoint operator.

```
class rasterio.coords.BoundingBox(left, bottom, right, top)
```

Bases: `tuple`

Bounding box named tuple, defining extent in cartesian coordinates.

```
BoundingBox(left, bottom, right, top)
```

left

Left coordinate

bottom

Bottom coordinate

right

Right coordinate

top

Top coordinate

bottom

Alias for field number 1

left

Alias for field number 0

right

Alias for field number 2

top

Alias for field number 3

rasterio.coords.disjoint_bounds(bounds1, bounds2)

Compare two bounds and determine if they are disjoint.

Parameters

- **bounds1** (*4-tuple*) – rasterio bounds tuple (left, bottom, right, top)
- **bounds2** (*4-tuple*) – rasterio bounds tuple

Returns

- *boolean*
- True if bounds are disjoint,
- False if bounds overlap

rasterio.crs module

Coordinate reference systems, the CRS class and supporting functions.

A coordinate reference system (CRS) defines how a dataset’s pixels map to locations on, for example, a globe or the Earth. A CRS may be local or global. The GIS field shares a number of authority files that define CRS. “EPSG:32618” is the name of a regional CRS from the European Petroleum Survey Group authority file. “OGC:CRS84” is the name of a global CRS from the Open Geospatial Consortium authority. Custom CRS can be described in text using several formats. Rasterio’s CRS class is our abstraction for coordinate reference systems.

A rasterio dataset’s crs property is an instance of CRS. CRS are also used to define transformations between coordinate reference systems. These transformations are performed by the PROJ library. Rasterio does not call PROJ functions directly, but invokes them via calls to GDAL’s “OSR*” functions.

class rasterio.crs.CRS(initialdata=None, **kwargs)

Bases: `object`

A geographic or projected coordinate reference system.

CRS objects may be created by passing PROJ parameters as keyword arguments to the standard constructor or by passing EPSG codes, PROJ mappings, PROJ strings, or WKT strings to the from_epsg, from_dict, from_string, or from_wkt static methods.

Examples

The from_dict method takes PROJ parameters as keyword arguments.

```
>>> crs = CRS.from_dict(proj="aea")
```

EPSG codes may be used with the from_epsg method.

```
>>> crs = CRS.from_epsg(3005)
```

The from_string method takes a variety of input.

```
>>> crs = CRS.from_string("EPSG:3005")
```

data

A PROJ4 dict representation of the CRS.

static from_authority(auth_name, code)

Make a CRS from an authority name and code.

New in version 1.1.7.

Parameters

- **auth_name** (*str*) – The name of the authority.
- **code** (*int or str*) – The code used by the authority.

Return type

CRS

Raises

CRSError –

static from_dict(initialdata=None, **kwargs)

Make a CRS from a dict of PROJ parameters or PROJ JSON.

Parameters

- **initialdata** (*mapping, optional*) – A dictionary or other mapping
- **kwargs** (*mapping, optional*) – Another mapping. Will be overlaid on the initialdata.

Return type

CRS

Raises

CRSError –

static from_epsg(code)

Make a CRS from an EPSG code.

Parameters

- code** (*int or str*) – An EPSG code. Strings will be converted to integers.

Notes

The input code is not validated against an EPSG database.

Return type

CRS

Raises

CRSError –

static from_proj4(*proj*)

Make a CRS from a PROJ4 string.

Parameters

proj (*str*) – A PROJ4 string like “+proj=longlat …”

Return type

CRS

Raises

CRSError –

static from_string(*value*, *morph_from_esri_dialect=False*)

Make a CRS from an EPSG, PROJ, or WKT string

Parameters

- **value** (*str*) – An EPSG, PROJ, or WKT string.
- **morph_from_esri_dialect** (*bool*, *optional*) – If True, items in the input using Esri’s dialect of WKT will be replaced by OGC standard equivalents.

Return type

CRS

Raises

CRSError –

static from_user_input(*value*, *morph_from_esri_dialect=False*)

Make a CRS from a variety of inputs.

Parameters

- **value** (*object*) – User input of many different kinds.
- **morph_from_esri_dialect** (*bool*, *optional*) – If True, items in the input using Esri’s dialect of WKT will be replaced by OGC standard equivalents.

Return type

CRS

Raises

CRSError –

static from_wkt(*wkt*, *morph_from_esri_dialect=False*)

Make a CRS from a WKT string.

Parameters

- **wkt** (*str*) – A WKT string.
- **morph_from_esri_dialect** (*bool*, *optional*) – If True, items in the input using Esri’s dialect of WKT will be replaced by OGC standard equivalents.

Return type`CRS`**Raises**`CRSError` –**get(*self*, *item*)****is_epsg_code**

Test if the CRS is defined by an EPSG code.

Return type`bool`**is_geographic**

Test if the CRS is a geographic coordinate reference system.

Return type`bool`**Raises**`CRSError` –**is_projected**

Test if the CRS is a projected coordinate reference system.

Return type`bool`**Raises**`CRSError` –**is_valid**

Test that the CRS is a geographic or projected CRS.

Return type`bool`**items(*self*)****linear_units**

Get a short name for the linear units of the CRS.

Returns`units` – “m”, “ft”, etc.**Return type**`str`**Raises**`CRSError` –**linear_units_factor**

Get linear units and the conversion factor to meters of the CRS.

Returns

- `units` (`str`) – “m”, “ft”, etc.
- `factor` (`float`) – Ratio of one unit to one meter.

Raises`CRSError` –

to_authority(*self*, *confidence_threshold*=70)

Convert to the best match authority name and code.

For a CRS created using an EPSG code, that same value is returned. For other CRS, including custom CRS, an attempt is made to match it to definitions in authority files. Matches with a confidence below the threshold are discarded.

Parameters

confidence_threshold (*int*) – Percent match confidence threshold (0-100).

Returns

- **name** (*str*) – Authority name.
- **code** (*str*) – Code from the authority file.
- or *None*

to_dict(*self*, *projjson*=*False*)

Convert CRS to a PROJ dict.

Note: If there is a corresponding EPSG code, it will be used when returning PROJ parameter dict.

New in version 1.3.0.

Parameters

projjson (*bool*, *default=False*) – If True, will convert to PROJ JSON dict (Requires GDAL 3.1+ and PROJ 6.2+). If False, will convert to PROJ parameter dict.

Return type

dict

to_epsg(*self*, *confidence_threshold*=70)

Convert to the best match EPSG code.

For a CRS created using an EPSG code, that same value is returned. For other CRS, including custom CRS, an attempt is made to match it to definitions in the EPSG authority file. Matches with a confidence below the threshold are discarded.

Parameters

confidence_threshold (*int*) – Percent match confidence threshold (0-100).

Return type

int or *None*

Raises

[CRSError](#) –

to_proj4(*self*)

Convert to a PROJ4 representation.

Return type

str

to_string(*self*)

Convert to a PROJ4 or WKT string.

The output will be reduced as much as possible by attempting a match to CRS defined in authority files.

Notes

Mapping keys are tested against the `all_proj_keys` list. Values of `True` are omitted, leaving the key bare: `{'no_defs': True}` -> “+no_defs” and items where the value is otherwise not a str, int, or float are omitted.

Return type

`str`

Raises

`CRSError` –

`to_wkt(self, morph_to_esri_dialect=False, version=None)`

Convert to a OGC WKT representation.

New in version 1.3.0: `version`

Parameters

- `morph_to_esri_dialect` (`bool`, *optional*) – Whether or not to morph to the Esri dialect of WKT Only applies to GDAL versions < 3. This parameter will be removed in a future version of rasterio.
- `version` (`WktVersion` or `str`, *optional*) – The version of the WKT output. Only works with GDAL 3+. Default is `WKT1_GDAL`.

Return type

`str`

Raises

`CRSError` –

`units_factor`

Get units and the conversion factor of the CRS.

Returns

- `units` (`str`) – “m”, “ft”, etc.
- `factor` (`float`) – Ratio of one unit to one radian if the CRS is geographic otherwise, it is to one meter.

Raises

`CRSError` –

`wkt`

An OGC WKT representation of the CRS

Return type

`str`

`rasterio.crs.epsg_treats_as_latlong(input_crs)`

Test if the CRS is in latlon order

From GDAL docs:

> This method returns TRUE if EPSG feels this geographic coordinate system should be treated as having lat/long coordinate ordering.

> Currently this returns TRUE for all geographic coordinate systems with an EPSG code set, and axes set defining it as lat, long.

> FALSE will be returned for all coordinate systems that are not geographic, or that do not have an EPSG code set.

> Note

> Important change of behavior since GDAL 3.0. In previous versions, geographic CRS imported with importFromEPSG() would cause this method to return FALSE on them, whereas now it returns TRUE, since importFromEPSG() is now equivalent to importFromEPSGA().

Parameters

input_crs ([CRS](#)) – Coordinate reference system, as a rasterio CRS object Example: CRS({‘init’: ‘EPSG:4326’})

Return type

[bool](#)

rasterio.crs.epsg_treats_as_northingeasting(*input_crs*)

Test if the CRS should be treated as having northing/easting coordinate ordering

From GDAL docs:

> This method returns TRUE if EPSG feels this projected coordinate system should be treated as having northing/easting coordinate ordering.

> Currently this returns TRUE for all projected coordinate systems with an EPSG code set, and axes set defining it as northing, easting.

> FALSE will be returned for all coordinate systems that are not projected, or that do not have an EPSG code set.

> Note

> Important change of behavior since GDAL 3.0. In previous versions, projected CRS with northing, easting axis order imported with importFromEPSG() would cause this method to return FALSE on them, whereas now it returns TRUE, since importFromEPSG() is now equivalent to importFromEPSGA().

Parameters

input_crs ([CRS](#)) – Coordinate reference system, as a rasterio CRS object Example: CRS({‘init’: ‘EPSG:4326’})

Return type

[bool](#)

rasterio.drivers module**Driver policies and utilities**

GDAL has many standard and extension format drivers and completeness of these drivers varies greatly. It’s possible to succeed poorly with some formats and drivers, meaning that easy problems can be solved but that harder problems are blocked by limitations of the drivers and formats.

NetCDF writing, for example, is presently blacklisted. Rasterio users should use netcdf4-python instead: <http://unidata.github.io/netcdf4-python/>.

rasterio.drivers.driver_from_extension(*path*)

Attempt to auto-detect driver based on the extension.

Parameters

path ([str](#) or [pathlike object](#)) – The path to the dataset to write with.

Returns

The name of the driver for the extension.

Return type

[str](#)

`rasterio.drivers.is_blacklisted(name, mode)`

Returns True if driver *name* and *mode* are blacklisted.

`rasterio.drivers.raster_driver_extensions()`**Returns**

Map of extensions to the driver.

Return type

dict

rasterio.dtypes module

Mapping of GDAL to Numpy data types.

Since 0.13 we are not importing numpy here and data types are strings. Happily strings can be used throughout Numpy and so existing code will not break.

`rasterio.dtypes.can_cast_dtype(values, dtype)`

Test if values can be cast to dtype without loss of information.

Parameters

- **values** (*list-like*) –
- **dtype** (*numpy dtype or string*) –

Returns

True if values can be cast to data type.

Return type

boolean

`rasterio.dtypes.check_dtype(dt)`

Check if dtype is a known dtype.

`rasterio.dtypes.get_minimum_dtype(values)`

Determine minimum type to represent values.

Uses range checking to determine the minimum integer or floating point data type required to represent values.

Parameters

values (*list-like*) –

Return type

rasterio dtype string

`rasterio.dtypes.in_dtype_range(value, dtype)`

Test if the value is within the dtype's range of values, Nan, or Inf.

`rasterio.dtypes.is_ndarray(array)`

Check if array is a ndarray.

`rasterio.dtypes.validate_dtype(values, valid_dtypes)`

Test if dtype of values is one of valid_dtypes.

Parameters

- **values** (*list-like*) –
- **valid_dtypes** (*list-like*) – list of valid dtype strings, e.g., ('int16', 'int32')

Returns

True if dtype of values is one of valid_dtypes

Return type

boolean

rasterio.enums module

Enumerations.

```
class rasterio.enums.ColorInterp(value, names=None, *, module=None, qualname=None, type=None,
                                 start=1, boundary=None)
```

Bases: `IntEnum`

Raster band color interpretation.

`Cb` = 15

`Cr` = 16

`Y` = 14

`alpha` = 6

`black` = 13

`blue` = 5

`cyan` = 10

`gray` = 1

`green` = 4

`grey` = 1

`hue` = 7

`lightness` = 9

`magenta` = 11

`palette` = 2

`red` = 3

`saturation` = 8

`undefined` = 0

`yellow` = 12

```
class rasterio.enums.Compression(value, names=None, *, module=None, qualname=None, type=None,
                                 start=1, boundary=None)
```

Bases: `Enum`

Available compression algorithms.

`ccittfax3` = 'CCITTFAZ3'

```

ccittfax4 = 'CCITTFAX4'
ccittrle = 'CCITTRLE'
deflate = 'DEFLATE'
jpeg = 'JPEG'
jpeg2000 = 'JPEG2000'
lerc = 'LERC'
lerc_deflate = 'LERC_DEFLATE'
lerc_zstd = 'LERC_ZSTD'
lzma = 'LZMA'
lzw = 'LZW'
none = 'NONE'
packbits = 'PACKBITS'
webp = 'WEBP'
zstd = 'ZSTD'

class rasterio.enums.Interleaving(value, names=None, *, module=None, qualname=None, type=None,
                                   start=1, boundary=None)
Bases: Enum
band = 'BAND'
line = 'LINE'
pixel = 'PIXEL'

class rasterio.enums.MaskFlags(value, names=None, *, module=None, qualname=None, type=None,
                               start=1, boundary=None)
Bases: IntEnum
all_valid = 1
alpha = 4
nodata = 8
per_dataset = 2

class rasterio.enums.MergeAlg(value, names=None, *, module=None, qualname=None, type=None, start=1,
                             boundary=None)
Bases: Enum
Available rasterization algorithms
add = 'ADD'
replace = 'REPLACE'

```

```
class rasterio.enums.PhotometricInterp(value, names=None, *, module=None, qualname=None,
                                         type=None, start=1, boundary=None)
```

Bases: [Enum](#)

black = 'MINISBLACK'

cielab = 'CIELAB'

cmyk = 'CMYK'

icclab = 'ICCLAB'

itulab = 'ITULAB'

rgb = 'RGB'

white = 'MINISWHITE'

ycbcr = 'YCbCr'

```
class rasterio.enums.Resampling(value, names=None, *, module=None, qualname=None, type=None,
                                 start=1, boundary=None)
```

Bases: [IntEnum](#)

Available warp resampling algorithms.

nearest

Nearest neighbor resampling (default, fastest algorithm, worst interpolation quality).

bilinear

Bilinear resampling.

cubic

Cubic resampling.

cubic_spline

Cubic spline resampling.

lanczos

Lanczos windowed sinc resampling.

average

Average resampling, computes the weighted average of all non-NODATA contributing pixels.

mode

Mode resampling, selects the value which appears most often of all the sampled points.

gauss

Gaussian resampling, Note: not available to the functions in rio.warp.

max

Maximum resampling, selects the maximum value from all non-NODATA contributing pixels. (GDAL >= 2.0)

min

Minimum resampling, selects the minimum value from all non-NODATA contributing pixels. (GDAL >= 2.0)

med

Median resampling, selects the median value of all non-NODATA contributing pixels. (GDAL >= 2.0)

q1

Q1, first quartile resampling, selects the first quartile value of all non-NODATA contributing pixels. (GDAL >= 2.0)

q3

Q3, third quartile resampling, selects the third quartile value of all non-NODATA contributing pixels. (GDAL >= 2.0)

sum

Sum, compute the weighted sum of all non-NODATA contributing pixels. (GDAL >= 3.1)

rms

RMS, root mean square / quadratic mean of all non-NODATA contributing pixels. (GDAL >= 3.3)

Notes

The first 8, ‘nearest’, ‘bilinear’, ‘cubic’, ‘cubic_spline’, ‘lanczos’, ‘average’, ‘mode’, and ‘gauss’, are available for making dataset overviews.

‘max’, ‘min’, ‘med’, ‘q1’, ‘q3’ are only supported in GDAL >= 2.0.0.

‘nearest’, ‘bilinear’, ‘cubic’, ‘cubic_spline’, ‘lanczos’, ‘average’, ‘mode’ are always available (GDAL >= 1.10).

‘sum’ is only supported in GDAL >= 3.1.

‘rms’ is only supported in GDAL >= 3.3.

Note: ‘gauss’ is not available to the functions in rio.warp.

average = 5

bilinear = 1

cubic = 2

cubic_spline = 3

gauss = 7

lanczos = 4

max = 8

med = 10

min = 9

mode = 6

nearest = 0

q1 = 11

q3 = 12

rms = 14

sum = 13

```
class rasterio.enums.TransformDirection(value, names=None, *, module=None, qualname=None,
                                         type=None, start=1, boundary=None)
```

Bases: [IntEnum](#)

Coordinate transform direction

Forward transform direction defined as image pixel (row, col) to geographic/projected (x, y) coordinates. Reverse transform direction defined as geographic/projected (x, y) to image pixel (row, col) coordinates.

Notes

The convention for transform direction for RPC based coordinate transform is typically the opposite of what is previously described. For consistency all coordinate transforms methods use the same convention.

forward = 1

reverse = 0

```
class rasterio.enums.TransformMethod(value, names=None, *, module=None, qualname=None, type=None,
                                         start=1, boundary=None)
```

Bases: [Enum](#)

affine = 'transform'

gcps = 'gcps'

rpacs = 'rpacs'

```
class rasterio.enums.WktVersion(value, names=None, *, module=None, qualname=None, type=None,
                                         start=1, boundary=None)
```

Bases: [Enum](#)

New in version 1.3.0.

Supported CRS WKT string versions

WKT1 = 'WKT1'

Alias for WKT Version 1 GDAL Style

WKT1_ESRI = 'WKT1_ESRI'

WKT Version 1 ESRI Style

WKT1_GDAL = 'WKT1_GDAL'

WKT Version 1 GDAL Style

WKT2 = 'WKT2'

Alias for latest WKT Version 2

WKT2_2015 = 'WKT2_2015'

WKT Version 2 from 2015

WKT2_2019 = 'WKT2_2018'

WKT Version 2 from 2019

rasterio.env module

Rasterio's GDAL/AWS environment

```
class rasterio.env.Env(session=None, aws_unsigned=False, profile_name=None, session_class=<function Session.aws_or_dummy>, **options)
```

Bases: `object`

Abstraction for GDAL and AWS configuration

The GDAL library is stateful: it has a registry of format drivers, an error stack, and dozens of configuration options.

Rasterio's approach to working with GDAL is to wrap all the state up using a Python context manager (see PEP 343, <https://www.python.org/dev/peps/pep-0343/>). When the context is entered GDAL drivers are registered, error handlers are configured, and configuration options are set. When the context is exited, drivers are removed from the registry and other configurations are removed.

Example

```
with rasterio.Env(GDAL_CACHEMAX=128000000) as env:
    # All drivers are registered, GDAL's raster block cache
    # size is set to 128 MB.
    # Commence processing...
    ...
    # End of processing.

# At this point, configuration options are set to their
# previous (possibly unset) values.
```

A `boto3` session or `boto3` session constructor arguments `aws_access_key_id`, `aws_secret_access_key`, `aws_session_token` may be passed to `Env`'s constructor. In the latter case, a session will be created as soon as needed. AWS credentials are configured for GDAL as needed.

`credentialize()`

Get credentials and configure GDAL

Note well: this method is a no-op if the GDAL environment already has credentials, unless session is not `None`.

Return type

`None`

`classmethod default_options()`

Default configuration options

Parameters

`None` –

Return type

`dict`

`drivers()`

Return a mapping of registered drivers.

`classmethod from_defaults(*args, **kwargs)`

Create an environment with default config options

Parameters

- **args** (*optional*) – Positional arguments for Env()
- **kwargs** (*optional*) – Keyword arguments for Env()

Return type*Env***Notes**

The items in kwargs will be overlaid on the default values.

class rasterio.env.GDALVersion(major=0, minor=0)Bases: *object*

Convenience class for obtaining GDAL major and minor version components and comparing between versions. This is highly simplistic and assumes a very normal numbering scheme for versions and ignores everything except the major and minor components.

at_least(other)**major****minor****classmethod parse(input)**

Parses input tuple or string to GDALVersion. If input is a GDALVersion instance, it is returned.

Parameters

input (*tuple of (major, minor), string, or instance of GDALVersion*) –

Return type*GDALVersion instance***classmethod runtime()**

Return GDALVersion of current GDAL runtime

class rasterio.env.NullContextManagerBases: *object***class rasterio.env.ThreadEnv**Bases: *_local***rasterio.env.defenv(**options)**

Create a default environment if necessary.

rasterio.env.delenv()

Delete options in the existing environment.

rasterio.env.ensure_env(f)

A decorator that ensures an env exists before a function calls any GDAL C functions.

rasterio.env.ensure_env_credentialled(f)

DEPRECATED alias for ensure_env_with_credentials

rasterio.env.ensure_env_with_credentials(f)

Ensures a config environment exists and is credentialized

Parameters

f (*function*) – A function.

Return type

A function wrapper.

Notes

The function wrapper checks the first argument of f and credentializes the environment if the first argument is a URI with scheme “s3”.

rasterio.env.env_ctx_if_needed()

Return an Env if one does not exist

Return type

Env or a do-nothing context manager

rasterio.env.getenv()

Get a mapping of current options.

rasterio.env.hascreds()**rasterio.env.hasenv()****rasterio.env.require_gdal_version(*version*, *param=None*, *values=None*, *is_max_version=False*, *reason=None*)**

A decorator that ensures the called function or parameters are supported by the runtime version of GDAL. Raises GDALVersionError if conditions are not met.

Examples

```
@require_gdal_version('2.2')
def some_func():
```

calling *some_func* with a runtime version of GDAL that is < 2.2 raises a GDALVersionError.

```
@require_gdal_version('2.2', param='foo')
def some_func(foo='bar'):
```

calling *some_func* with parameter *foo* of any value on GDAL < 2.2 raises a GDALVersionError.

```
@require_gdal_version('2.2', param='foo', values=('bar',))
def some_func(foo=None):
```

calling *some_func* with parameter *foo* and value *bar* on GDAL < 2.2 raises a GDALVersionError.

Parameters

- **version** (*tuple*, *string*, or *GDALVersion*) –
- **param** (*string (optional, default: None)*) – If *values* are absent, then all use of this parameter with a value other than default value requires at least GDAL *version*.
- **values** (*tuple*, *list*, or *set (optional, default: None)*) – contains values that require at least GDAL *version*. *param* is required for *values*.
- **is_max_version** (*bool (optional, default: False)*) – if *True* indicates that the version provided is the maximum version allowed, instead of requiring at least that version.

- **reason(string optional: default: "")** – custom error message presented to user in addition to message about GDAL version. Use this to provide an explanation of what changed if necessary context to the user.

Return type

wrapped function

rasterio.env.setenv(options)**

Set options in the existing environment.

rasterio.errors module

Errors and Warnings.

exception rasterio.errors.BandOverviewErrorBases: [UserWarning](#)

Raised when a band overview access fails.

exception rasterio.errors.CRSErrorBases: [ValueError](#)

Raised when a CRS string or mapping is invalid or cannot serve to define a coordinate transformation.

exception rasterio.errors.DatasetAttributeErrorBases: [RasterioError](#), [NotImplementedError](#)

Raised when dataset attributes are misused

exception rasterio.errors.DatasetIOShapeErrorBases: [RasterioError](#)

Raised when data buffer shape is a mismatch when reading and writing

exception rasterio.errors.DriverCapabilityErrorBases: [RasterioError](#), [ValueError](#)

Raised when a format driver can't a feature such as writing.

exception rasterio.errors.DriverRegistrationErrorBases: [ValueError](#)

Raised when a format driver is requested but is not registered.

exception rasterio.errors.EnvErrorBases: [RasterioError](#)

Raised when the state of GDAL/AWS environment cannot be created or modified.

exception rasterio.errors.FileOverwriteError(message)Bases: [FileError](#)

Raised when Rasterio's CLI refuses to clobber output files.

exception rasterio.errors.GDALBehaviorChangeExceptionBases: [RuntimeError](#)

Raised when GDAL's behavior differs from the given arguments. For example, antimeridian cutting is always on as of GDAL 2.2.0. Users expecting it to be off will be presented with a MultiPolygon when the rest of their code expects a Polygon.

Examples

```
# Raises an exception on GDAL >= 2.2.0
rasterio.warp.transform_geometry(
    src_crs, dst_crs, antimeridian_cutting=False)
```

`exception rasterio.errors.GDALOptionNotImplementedError`

Bases: `RasterioError`

A dataset opening or dataset creation option can't be supported

This will be raised from Rasterio's shim modules. For example, when a user passes arguments to `open_dataset()` that can't be evaluated by GDAL 1.x.

`exception rasterio.errors.GDALVersionError`

Bases: `RasterioError`

Raised if the runtime version of GDAL does not meet the required version of GDAL.

`exception rasterio.errors.InvalidArrayError`

Bases: `RasterioError`

Raised when methods are passed invalid arrays

`exception rasterio.errors.NodataShadowWarning`

Bases: `UserWarning`

Warn that a dataset's nodata attribute is shadowing its alpha band.

`exception rasterio.errors.NotGeoreferencedWarning`

Bases: `UserWarning`

Warn that a dataset isn't georeferenced.

`exception rasterio.errors.OverviewCreationError`

Bases: `RasterioError`

Raised when creation of an overview fails

`exception rasterio.errors.PathError`

Bases: `RasterioError`

Raised when a dataset path is malformed or invalid

`exception rasterio.errors.RPCError`

Bases: `ValueError`

Raised when RPC transformation is invalid

`exception rasterio.errors.RasterBlockError`

Bases: `RasterioError`

Raised when raster block access fails

`exception rasterio.errors.RasterioDeprecationWarning`

Bases: `FutureWarning`

Rasterio module deprecations

Following <https://www.python.org/dev/peps/pep-0565/#additional-use-case-for-futurewarning> we base this on `FutureWarning` while continuing to support Python < 3.7.

exception rasterio.errors.RasterioError

Bases: [Exception](#)

Root exception class

exception rasterio.errors.RasterioIOError

Bases: [OSError](#)

Raised when a dataset cannot be opened using one of the registered format drivers.

exception rasterio.errors.ResamplingAlgorithmError

Bases: [RasterioError](#)

Raised when a resampling algorithm is invalid or inapplicable

exception rasterio.errors.ShapeSkipWarning

Bases: [UserWarning](#)

Warn that an invalid or empty shape in a collection has been skipped

exception rasterio.errors.StatisticsError

Bases: [RasterioError](#)

Raised when dataset statistics cannot be computed.

exception rasterio.errors.TransformError

Bases: [RasterioError](#)

Raised when transform arguments are invalid

exception rasterio.errors.TransformWarning

Bases: [UserWarning](#)

Warn that coordinate transformations may behave unexpectedly

exception rasterio.errors.UnsupportedOperation

Bases: [RasterioError](#)

Raised when reading from a file opened in ‘w’ mode

exception rasterio.errors.WarpOperationError

Bases: [RasterioError](#)

Raised when a warp operation fails.

exception rasterio.errors.WarpOptionsError

Bases: [RasterioError](#)

Raised when options for a warp operation are invalid

exception rasterio.errors.WarpedVRTError

Bases: [RasterioError](#)

Raised when WarpedVRT can’t be initialized

exception rasterio.errors.WindowError

Bases: [RasterioError](#)

Raised when errors occur during window operations

exception rasterio.errors.WindowEvaluationError

Bases: [ValueError](#)

Raised when window evaluation fails

rasterio.features module

Functions for working with features in a raster dataset.

`rasterio.features.bounds(geometry, north_up=True, transform=None)`

Return a (left, bottom, right, top) bounding box.

From Fiona 1.4.8. Modified to return bbox from geometry if available.

Parameters

- `geometry (GeoJSON-like feature (implements __geo_interface__),)` – feature collection, or geometry.

Returns

Bounding box: (left, bottom, right, top)

Return type

`tuple`

`rasterio.features.dataset_features(src, bidx=None, sampling=1, band=True, as_mask=False, with_nodata=False, geographic=True, precision=-1)`

Yield GeoJSON features for the dataset

The geometries are polygons bounding contiguous regions of the same raster value.

Parameters

- `src (Rasterio Dataset)` –
- `bidx (int)` – band index
- `sampling (int (DEFAULT: 1))` – Inverse of the sampling fraction; a value of 10 decimates
- `band (boolean (DEFAULT: True))` – extract features from a band (True) or a mask (False)
- `as_mask (boolean (DEFAULT: False))` – Interpret band as a mask and output only one class of valid data shapes?
- `with_nodata (boolean (DEFAULT: False))` – Include nodata regions?
- `geographic (str (DEFAULT: True))` – Output shapes in EPSG:4326? Otherwise use the native CRS.
- `precision (int (DEFAULT: -1))` – Decimal precision of coordinates. -1 for full float precision output

Yields

GeoJSON-like Feature dictionaries for shapes found in the given band

`rasterio.features.geometry_mask(geometries, out_shape, transform, all_touched=False, invert=False)`

Create a mask from shapes.

By default, mask is intended for use as a numpy mask, where pixels that overlap shapes are False.

Parameters

- `geometries (iterable over geometries (GeoJSON-like objects))` –
- `out_shape (tuple or list)` – Shape of output numpy ndarray.
- `transform (Affine transformation object)` – Transformation from pixel coordinates of *source* to the coordinate system of the input *shapes*. See the *transform* property of dataset objects.

- **all_touched** (*boolean, optional*) – If True, all pixels touched by geometries will be burned in. If false, only pixels whose center is within the polygon or that are selected by Bresenham’s line algorithm will be burned in.
- **invert** (*boolean, optional*) – If True, mask will be True for pixels that overlap shapes. False by default.

Returns

Result

Return type

numpy ndarray of type ‘bool’

Notes

See rasterize() for performance notes.

```
rasterio.features.geometry_window(dataset, shapes, pad_x=0, pad_y=0, north_up=None, rotated=None,  
pixel_precision=None, boundless=False)
```

Calculate the window within the raster that fits the bounds of the geometry plus optional padding. The window is the outermost pixel indices that contain the geometry (floor of offsets, ceiling of width and height).

If shapes do not overlap raster, a WindowError is raised.

Parameters

- **dataset** (*dataset object opened in ‘r’ mode*) – Raster for which the mask will be created.
- **shapes** (*iterable over geometries.*) – A geometry is a GeoJSON-like object or implements the geo interface. Must be in same coordinate system as dataset.
- **pad_x** (*float*) – Amount of padding (as fraction of raster’s x pixel size) to add to left and right side of bounds.
- **pad_y** (*float*) – Amount of padding (as fraction of raster’s y pixel size) to add to top and bottom of bounds.
- **north_up** (*optional*) – This parameter is ignored since version 1.2.1. A deprecation warning will be emitted in 1.3.0.
- **rotated** (*optional*) – This parameter is ignored since version 1.2.1. A deprecation warning will be emitted in 1.3.0.
- **pixel_precision** (*int or float, optional*) – Number of places of rounding precision or absolute precision for evaluating bounds of shapes.
- **boundless** (*bool, optional*) – Whether to allow a boundless window or not.

Return type*rasterio.windows.Window*

```
rasterio.features.is_valid_geom(geom)
```

Checks to see if geometry is a valid GeoJSON geometry type or GeometryCollection. Geometry must be GeoJSON or implement the geo interface.

Geometries must be non-empty, and have at least x, y coordinates.

Note: only the first coordinate is checked for validity.

Parameters

geom (*an object that implements the geo interface or GeoJSON-like object*)

—

Returns

bool

Return type

True if object is a valid GeoJSON geometry type

```
rasterio.features.rasterize(shapes, out_shape=None, fill=0, out=None, transform=(1.0, 0.0, 0.0, 0.0, 0.0, 1.0,
    0.0, 0.0, 0.0, 1.0), all_touched=False, merge_alg=MergeAlg.replace,
    default_value=1, dtype=None)
```

Return an image array with input geometries burned in.

Warnings will be raised for any invalid or empty geometries, and an exception will be raised if there are no valid shapes to rasterize.

Parameters

- **shapes** (*iterable of (geometry, value) pairs or geometries*) – The *geometry* can either be an object that implements the geo interface or GeoJSON-like object. If no *value* is provided the *default_value* will be used. If *value* is *None* the *fill* value will be used.
- **out_shape** (*tuple or list with 2 integers*) – Shape of output numpy ndarray.
- **fill** (*int or float, optional*) – Used as fill value for all areas not covered by input geometries.
- **out** (*numpy ndarray, optional*) – Array of same shape and data type as *source* in which to store results.
- **transform** (*Affine transformation object, optional*) – Transformation from pixel coordinates of *source* to the coordinate system of the input *shapes*. See the *transform* property of dataset objects.
- **all_touched** (*boolean, optional*) – If True, all pixels touched by geometries will be burned in. If false, only pixels whose center is within the polygon or that are selected by Bresenham's line algorithm will be burned in.
- **merge_alg** (*MergeAlg, optional*) –

Merge algorithm to use. One of:**MergeAlg.replace (default):**

the new value will overwrite the existing value.

MergeAlg.add:

the new value will be added to the existing raster.

- **default_value** (*int or float, optional*) – Used as value for all geometries, if not provided in *shapes*.
- **dtype** (*rasterio or numpy data type, optional*) – Used as data type for results, if *out* is not provided.

Returns

If *out* was not *None* then *out* is returned, it will have been modified in-place. If *out* was *None*, this will be a new array.

Return type

numpy ndarray

Notes

Valid data types for *fill*, *default_value*, *out*, *dtype* and shape values are “int16”, “int32”, “uint8”, “uint16”, “uint32”, “float32”, and “float64”.

This function requires significant memory resources. The shapes iterator will be materialized to a Python list and another C copy of that list will be made. The *out* array will be copied and additional temporary raster memory equal to 2x the smaller of *out* data or GDAL’s max cache size (controlled by GDAL_CACHEMAX, default is 5% of the computer’s physical memory) is required.

If GDAL max cache size is smaller than the output data, the array of shapes will be iterated multiple times. Performance is thus a linear function of buffer size. For maximum speed, ensure that GDAL_CACHEMAX is larger than the size of *out* or *out_shape*.

```
rasterio.features.shapes(source, mask=None, connectivity=4, transform=(1.0, 0.0, 0.0, 0.0, 1.0, 0.0, 0.0, 0.0, 1.0))
```

Get shapes and values of connected regions in a dataset or array.

Parameters

- **source** (*array*, *dataset object*, *Band*, or *tuple*(*dataset*, *bidx*)) – Data type must be one of rasterio.int16, rasterio.int32, rasterio.uint8, rasterio.uint16, or rasterio.float32.
- **mask** (*numpy ndarray* or *rasterio Band object*, *optional*) – Must evaluate to bool (*rasterio.bool_* or *rasterio.uint8*). Values of False or 0 will be excluded from feature generation. Note well that this is the inverse sense from Numpy’s, where a mask value of True indicates invalid data in an array. If *source* is a Numpy masked array and *mask* is None, the source’s mask will be inverted and used in place of *mask*.
- **connectivity** (*int*, *optional*) – Use 4 or 8 pixel connectivity for grouping pixels into features
- **transform** (*Affine transformation*, *optional*) – If not provided, feature coordinates will be generated based on pixel coordinates

Yields

polygon, value – A pair of (polygon, value) for each feature found in the image. Polygons are GeoJSON-like dicts and the values are the associated value from the image, in the data type of the image. Note: due to floating point precision issues, values returned from a floating point image may not exactly match the original values.

Notes

The amount of memory used by this algorithm is proportional to the number and complexity of polygons produced. This algorithm is most appropriate for simple thematic data. Data with high pixel-to-pixel variability, such as imagery, may produce one polygon per pixel and consume large amounts of memory.

Because the low-level implementation uses either an int32 or float32 buffer, uint32 and float64 data cannot be operated on without truncation issues.

```
rasterio.features.sieve(source, size, out=None, mask=None, connectivity=4)
```

Remove small polygon regions from a raster.

Polygons are found for each set of neighboring pixels of the same value.

Parameters

- **source** (*ndarray, dataset, or Band*) – The source is a 2 or 3-D ndarray, a dataset opened in “r” mode, or a single or a multiple Rasterio Band object. Must be of type rasterio.int16, rasterio.int32, rasterio.uint8, rasterio.uint16, or rasterio.float32
- **size** (*int*) – minimum polygon size (number of pixels) to retain.
- **out** (*numpy ndarray, optional*) – Array of same shape and data type as *source* in which to store results.
- **mask** (*numpy ndarray or rasterio Band object, optional*) – Values of False or 0 will be excluded from feature generation Must evaluate to bool (**rasterio.bool_** or rasterio.uint8)
- **connectivity** (*int, optional*) – Use 4 or 8 pixel connectivity for grouping pixels into features

Returns**out** – Result**Return type**

numpy ndarray

Notes

GDAL only supports values that can be cast to 32-bit integers for this operation.

The amount of memory used by this algorithm is proportional to the number and complexity of polygons found in the image. This algorithm is most appropriate for simple thematic data. Data with high pixel-to-pixel variability, such as imagery, may produce one polygon per pixel and consume large amounts of memory.

rasterio.fill module

Fill holes in raster dataset by interpolation from the edges.

`rasterio.fill.fillnodata(image, mask=None, max_search_distance=100.0, smoothing_iterations=0)`

Fill holes in raster data by interpolation

This algorithm will interpolate values for all designated nodata pixels (marked by zeros in *mask*). For each pixel a four direction conic search is done to find values to interpolate from (using inverse distance weighting). Once all values are interpolated, zero or more smoothing iterations (3x3 average filters on interpolated pixels) are applied to smooth out artifacts.

This algorithm is generally suitable for interpolating missing regions of fairly continuously varying rasters (such as elevation models for instance). It is also suitable for filling small holes and cracks in more irregularly varying images (like aerial photos). It is generally not so great for interpolating a raster from sparse point data.

Parameters

- **image** (*numpy ndarray*) – The source image with holes to be filled. If a MaskedArray, the inverse of its mask will define the pixels to be filled – unless the **mask** argument is not None (see below).`
- **mask** (*numpy ndarray or None*) – A mask band indicating which pixels to interpolate. Pixels to interpolate into are indicated by the value 0. Values > 0 indicate areas to use during interpolation. Must be same shape as *image*. This array always takes precedence over the *image*’s mask (see above). If None, the inverse of the *image*’s mask will be used if available.
- **max_search_distance** (*float, optional*) – The maximum number of pixels to search in all directions to find values to interpolate from. The default is 100.

- **smoothing_iterations** (*integer, optional*) – The number of 3x3 smoothing filter passes to run. The default is 0.

Returns

out – The filled raster array.

Return type

numpy ndarray

rasterio.io module

Classes capable of reading and writing datasets

Instances of these classes are called dataset objects.

class rasterio.io.BufferedDatasetWriter

Bases: `BufferedDatasetWriterBase`, `WindowMethodsMixin`, `TransformMethodsMixin`

Maintains data and metadata in a buffer, writing to disk or network only when `close()` is called.

This allows incremental updates to datasets using formats that don't otherwise support updates, such as JPEG.

block_shapes

An ordered list of block shapes for each bands

Shapes are tuples and have the same ordering as the dataset's shape: (count of image rows, count of image columns).

Return type

list

block_size(bidx, i, j)

Returns the size in bytes of a particular block

Only useful for TIFF formatted datasets.

Parameters

- **bidx** (*int*) – Band index, starting with 1.
- **i** (*int*) – Row index of the block, starting with 0.
- **j** (*int*) – Column index of the block, starting with 0.

Return type

int

block_window(bidx, i, j)

Returns the window for a particular block

Parameters

- **bidx** (*int*) – Band index, starting with 1.
- **i** (*int*) – Row index of the block, starting with 0.
- **j** (*int*) – Column index of the block, starting with 0.

Return type

`Window`

block_windows(*bidx=0*)

Iterator over a band's blocks and their windows

The primary use of this method is to obtain windows to pass to `read()` for highly efficient access to raster block data.


The positional parameter `bidx` takes the index (starting at 1) of the desired band. This iterator yields blocks “left to right” and “top to bottom” and is similar to Python’s `enumerate()` in that the first element is the block index and the second is the dataset window.

Blocks are built-in to a dataset and describe how pixels are grouped within each band and provide a mechanism for efficient I/O. A window is a range of pixels within a single band defined by row start, row stop, column start, and column stop. For example, `((0, 2), (0, 2))` defines a 2 x 2 window at the upper left corner of a raster band. Blocks are referenced by an `(i, j)` tuple where `(0, 0)` would be a band’s upper left block.

Raster I/O is performed at the block level, so accessing a window spanning multiple rows in a striped raster requires reading each row. Accessing a 2 x 2 window at the center of a 1800 x 3600 image requires reading 2 rows, or 7200 pixels just to get the target 4. The same image with internal 256 x 256 blocks would require reading at least 1 block (if the window entire window falls within a single block) and at most 4 blocks, or at least 512 pixels and at most 2048.

Given an image that is 512 x 512 with blocks that are 256 x 256, its blocks and windows would look like:

Blocks:



Windows:

```
UL: ((0, 256), (0, 256))
UR: ((0, 256), (256, 512))
LL: ((256, 512), (0, 256))
LR: ((256, 512), (256, 512))
```

Parameters

`bidx` (`int`, *optional*) – The band index (using 1-based indexing) from which to extract windows. A value less than 1 uses the first band if all bands have homogeneous windows and raises an exception otherwise.

Yields

`block, window`

bounds

Returns the lower left and upper right bounds of the dataset in the units of its coordinate reference system.

The returned value is a tuple: (lower left x, lower left y, upper right x, upper right y)

build_overviews(*factors*, *resampling*=*Resampling.nearest*)

Build overviews at one or more decimation factors for all bands of the dataset.

checksum(*bidx*, *window*=*None*)

Compute an integer checksum for the stored band

Parameters

- **bidx** (*int*) – The band’s index (1-indexed).
- **window** (*tuple*, *optional*) – A window of the band. Default is the entire extent of the band.

Return type

An int.

close()

Close the dataset and unwind attached exit stack.

closed

Test if the dataset is closed

Return type

bool

colorinterp

A sequence of `ColorInterp.<enum>` in band order.

Return type

tuple

colormap(*bidx*)

Returns a dict containing the colormap for a band.

Parameters

- **bidx** (*int*) – Index of the band whose colormap will be returned. Band index starts at 1.

Returns

Mapping of color index value (starting at 0) to RGBA color as a 4-element tuple.

Return type

dict

Raises

- **ValueError** – If no colormap is found for the specified band (NULL color table).
- **IndexError** – If no band exists for the provided index.

compression**count**

The number of raster bands in the dataset

Return type

int

crs

The dataset’s coordinate reference system

In setting this property, the value may be a CRS object or an EPSG:nnnn or WKT string.

Return type*CRS*

```
dataset_mask(out=None, out_shape=None, window=None, boundless=False,
    resampling=Resampling.nearest)
```

Get the dataset's 2D valid data mask.

Parameters

- **out** (*numpy ndarray, optional*) – As with Numpy ufuncs, this is an optional reference to an output array with the same dimensions and shape into which data will be placed.

Note: the method's return value may be a view on this array. In other words, *out* is likely to be an incomplete representation of the method's results.

Cannot be combined with *out_shape*.

- **out_shape** (*tuple, optional*) – A tuple describing the output array's shape. Allows for decimated reads without constructing an output Numpy array.

Cannot be combined with *out*.

- **window** (*a pair (tuple) of pairs of ints or Window, optional*) – The optional *window* argument is a 2 item tuple. The first item is a tuple containing the indexes of the rows at which the window starts and stops and the second is a tuple containing the indexes of the columns at which the window starts and stops. For example, ((0, 2), (0, 2)) defines a 2x2 window at the upper left of the raster dataset.

- **boundless** (*bool, optional (default False)*) – If *True*, windows that extend beyond the dataset's extent are permitted and partially or completely filled arrays will be returned as appropriate.

- **resampling** (*Resampling*) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.

Returns

The dtype of this array is uint8. 0 = nodata, 255 = valid data.

Return type

Numpy ndarray or a view on a Numpy ndarray

Notes

Note: as with Numpy ufuncs, an object is returned even if you use the optional *out* argument and the return value shall be preferentially used by callers.

The dataset mask is calculated based on the individual band masks according to the following logic, in order of precedence:

1. If a .msk file, dataset-wide alpha, or internal mask exists it will be used for the dataset mask.
2. Else if the dataset is a 4-band with a shadow nodata value, band 4 will be used as the dataset mask.
3. If a nodata value exists, use the binary OR (|) of the band masks 4. If no nodata value exists, return a mask filled with 255.

Note that this differs from `read_masks` and GDAL RFC15 in that it applies per-dataset, not per-band (see https://trac.osgeo.org/gdal/wiki/rfc15_nodatabitmask)

descriptions

Descriptions for each dataset band

To set descriptions, one for each band is required.

Return type

list of str

driver**dtypes**

The data types of each band in index order

Return type

list of str

files

Returns a sequence of files associated with the dataset.

Return type

tuple

gcps

ground control points and their coordinate reference system.

This property is a 2-tuple, or pair: (gcps, crs).

gcps

[list of GroundControlPoint] Zero or more ground control points.

crs: CRS

The coordinate reference system of the ground control points.

get_gcps()

Get GCPs and their associated CRS.

get_nodatavals()**get_tag_item(ns, dm=None, bidx=0, ovr=None)**

Returns tag item value

Parameters

- **ns** (str) – The key for the metadata item to fetch.
- **dm** (str) – The domain to fetch for.
- **bidx** (int) – Band index, starting with 1.
- **ovr** (int) – Overview level

Return type

str

get_transform()

Returns a GDAL geotransform in its native form.

height**index(x, y, z=None, op=<built-in function floor>, precision=None, transform_method=TransformMethod.affine, **rpc_options)**

Get the (row, col) index of the pixel containing (x, y).

Parameters

- **x** (*float*) – x value in coordinate reference system
- **y** (*float*) – y value in coordinate reference system
- **z** (*float, optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **op** (*function, optional (default: math.floor)*) – Function to convert fractional pixels to whole numbers (floor, ceiling, round)
- **transform_method** (*TransformMethod, optional*) – The coordinate transformation method. Default: *TransformMethod.affine*.
- **rpc_options** (*dict, optional*) – Additional arguments passed to GDALCreateRPC-Transformer
- **precision** (*int, optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns

(row index, col index)

Return type

tuple

indexes

The 1-based indexes of each band in the dataset

For a 3-band dataset, this property will be [1, 2, 3].

Return type

list of int

interleaving**is_tiled****lnglat()****mask_flagEnums**

Sets of flags describing the sources of band masks.

Parameters

- **all_valid** (*There are no invalid pixels, all mask values will be* – 255. When used this will normally be the only flag set.)
- **per_dataset** (*The mask band is shared between all bands on the* – dataset.)
- **alpha** (*The mask band is actually an alpha band and may have* – values other than 0 and 255.)
- **nodata** (*Indicates the mask is actually being generated from* – nodata values (mutually exclusive of “alpha”).)

Returns

One list of rasterio.enums.MaskFlags members per band.

Return type

list [, list*]

Examples

For a 3 band dataset that has masks derived from nodata values:

```
>>> dataset.mask_flagEnums
([<MaskFlags.nodata: 8>], [<MaskFlags.nodata: 8>], [<MaskFlags.nodata: 8>])
>>> band1_flags = dataset.mask_flagEnums[0]
>>> rasterio.enums.MaskFlags.nodata in band1_flags
True
>>> rasterio.enums.MaskFlags.alpha in band1_flags
False
```

meta

The basic metadata of this dataset.

mode

name

nodata

The dataset's single nodata value

Notes

May be set.

Return type

float

nodatavals

Nodata values for each band

Notes

This may not be set.

Return type

list of float

offsets

Raster offset for each dataset band

To set offsets, one for each band is required.

Return type

list of float

options

overviews(*bidx*)

photometric

profile

Basic metadata and creation options of this dataset.

May be passed as keyword arguments to *rasterio.open()* to create a clone of this dataset.

```
read(indexes=None, out=None, window=None, masked=False, out_shape=None, boundless=False,  
      resampling=Resampling.nearest, fill_value=None, out_dtype=None)
```

Read band data and, optionally, mask as an array.

A smaller (or larger) region of the dataset may be specified and it may be resampled and/or converted to a different data type.

Parameters

- **indexes** (*int or list, optional*) – If *indexes* is a list, the result is a 3D array, but is a 2D array if it is a band index number.
- **out** (*numpy ndarray, optional*) – As with Numpy ufuncs, this is an optional reference to an output array into which data will be placed. If the height and width of *out* differ from that of the specified window (see below), the raster image will be decimated or replicated using the specified resampling method (also see below). This parameter cannot be combined with *out_shape*.
Note: the method's return value may be a view on this array. In other words, *out* is likely to be an incomplete representation of the method's results.
- **out_dtype** (*str or numpy dtype*) – The desired output data type. For example: 'uint8' or rasterio.uint16.
- **out_shape** (*tuple, optional*) – A tuple describing the shape of a new output array. See *out* (above) for notes on image decimation and replication. This parameter cannot be combined with *out*.
- **window** (*Window, optional*) – The region (slice) of the dataset from which data will be read. The default is the entire dataset.
- **masked** (*bool, optional*) – If *masked* is *True* the return value will be a masked array. Otherwise (the default) the return value will be a regular array. Masks will be exactly the inverse of the GDAL RFC 15 conforming arrays returned by *read_masks()*.
- **boundless** (*bool, optional (default False)*) – If *True*, windows that extend beyond the dataset's extent are permitted and partially or completely filled arrays will be returned as appropriate.
- **resampling** (*Resampling*) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.
- **fill_value** (*scalar*) – Fill value applied in the *boundless=True* case only. Like the *fill_value* of *numpy.ma.MaskedArray*, should be value valid for the dataset's data type.

Return type

Numpy ndarray or a view on a Numpy ndarray

Raises

RasterioIOError – If the write fails.

Notes

This data is read from the dataset's band cache, which means that repeated reads of the same windows may avoid I/O.

As with Numpy ufuncs, an object is returned even if you use the optional `out` argument and the return value shall be preferentially used by callers.

`read_crs()`

Return the GDAL dataset's stored CRS

`read_masks(indexes=None, out=None, out_shape=None, window=None, boundless=False, resampling=Resampling.nearest)`

Read band masks as an array.

A smaller (or larger) region of the dataset may be specified and it may be resampled and/or converted to a different data type.

Parameters

- **indexes** (`int` or `list`, `optional`) – If `indexes` is a list, the result is a 3D array, but is a 2D array if it is a band index number.
- **out** (`numpy ndarray`, `optional`) – As with Numpy ufuncs, this is an optional reference to an output array into which data will be placed. If the height and width of `out` differ from that of the specified window (see below), the raster image will be decimated or replicated using the specified resampling method (also see below). This parameter cannot be combined with `out_shape`.
Note: the method's return value may be a view on this array. In other words, `out` is likely to be an incomplete representation of the method's results.
- **out_shape** (`tuple`, `optional`) – A tuple describing the shape of a new output array. See `out` (above) for notes on image decimation and replication. This parameter cannot be combined with `out`.
- **window** (`Window`, `optional`) – The region (slice) of the dataset from which data will be read. The default is the entire dataset.
- **boundless** (`bool`, `optional` (default `False`)) – If `True`, windows that extend beyond the dataset's extent are permitted and partially or completely filled arrays will be returned as appropriate.
- **resampling** (`Resampling`) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.

Return type

Numpy ndarray or a view on a Numpy ndarray

Raises

`RasterioIOError` – If the write fails.

Notes

This data is read from the dataset’s band cache, which means that repeated reads of the same windows may avoid I/O.

As with Numpy ufuncs, an object is returned even if you use the optional *out* argument and the return value shall be preferentially used by callers.

`read_transform()`

Return the stored GDAL GeoTransform

`res`

Returns the (width, height) of pixels in the units of its coordinate reference system.

`rpcs`

Rational polynomial coefficients mapping between pixel and geodetic coordinates.

This property is a dict-like object.

`rpcs` : RPC instance containing coefficients. Empty if dataset does not have any metadata in the “RPC” domain.

`sample(xy, indexes=None, masked=False)`

Get the values of a dataset at certain positions

Values are from the nearest pixel. They are not interpolated.

Parameters

- `xy (iterable)` – Pairs of x, y coordinates (floats) in the dataset’s reference system.
- `indexes (int or list of int)` – Indexes of dataset bands to sample.
- `masked (bool, default: False)` – Whether to mask samples that fall outside the extent of the dataset.

Returns

Arrays of length equal to the number of specified indexes containing the dataset values for the bands corresponding to those indexes.

Return type

iterable

`scales`

Raster scale for each dataset band

To set scales, one for each band is required.

Return type

list of float

`set_band_description(bidx, value)`

Sets the description of a dataset band.

Parameters

- `bidx (int)` – Index of the band (starting with 1).
- `value (string)` – A description of the band.

Return type

None

set_band_unit(*bidx*, *value*)

Sets the unit of measure of a dataset band.

Parameters

- **bidx** (*int*) – Index of the band (starting with 1).
- **value** (*str*) – A label for the band’s unit of measure such as ‘meters’ or ‘degC’. See the Pint project for a suggested list of units.

Return type

None

shape**start()**

Start the dataset’s life cycle

statistics(*bidx*, *approx=False*, *clear_cache=False*)

Get min, max, mean, and standard deviation of a raster band.

Parameters

- **bidx** (*int*) – The band’s index (1-indexed).
- **approx** (*bool*, *optional*) – If True, statistics will be calculated from reduced resolution data.
- **clear_cache** (*bool*, *optional*) – If True, saved stats will be deleted and statistics will be recomputed. Requires GDAL version >= 3.2.

Return type

Statistics

Notes

GDAL will preferentially use statistics kept in raster metadata like images tags or an XML sidecar. If that metadata is out of date, the statistics may not correspond to the actual data.

Additionally, GDAL will save statistics to file metadata as a side effect if that metadata does not already exist.

stop()

Close the GDAL dataset handle

subdatasets

Sequence of subdatasets

tag_namespaces(*bidx=0*)

Get a list of the dataset’s metadata domains.

Returned items may be passed as *ns* to the tags method.

Parameters

- **int** (*bidx*) – Can be used to select a specific band, otherwise the dataset’s general metadata domains are returned.
- **optional** – Can be used to select a specific band, otherwise the dataset’s general metadata domains are returned.

Return type

list of str

tags(*bidx=0, ns=None*)

Returns a dict containing copies of the dataset or band's tags.

Tags are pairs of key and value strings. Tags belong to namespaces. The standard namespaces are: default (None) and 'IMAGE_STRUCTURE'. Applications can create their own additional namespaces.

The optional bidx argument can be used to select the tags of a specific band. The optional ns argument can be used to select a namespace other than the default.

transform

The dataset's georeferencing transformation matrix

This transform maps pixel row/column coordinates to coordinates in the dataset's coordinate reference system.

Return type

Affine

units

one units string for each dataset band

Possible values include 'meters' or 'degC'. See the Pint project for a suggested list of units.

To set units, one for each band is required.

Return type

list of str

Type

A list of str

update_tags(*bidx=0, ns=None, **kwargs*)

Updates the tags of a dataset or one of its bands.

Tags are pairs of key and value strings. Tags belong to namespaces. The standard namespaces are: default (None) and 'IMAGE_STRUCTURE'. Applications can create their own additional namespaces.

The optional bidx argument can be used to select the dataset band. The optional ns argument can be used to select a namespace other than the default.

width**window**(*left, bottom, right, top, precision=None*)

Get the window corresponding to the bounding coordinates.

The resulting window is not cropped to the row and column limits of the dataset.

Parameters

- **left** (*float*) – Left (west) bounding coordinate
- **bottom** (*float*) – Bottom (south) bounding coordinate
- **right** (*float*) – Right (east) bounding coordinate
- **top** (*float*) – Top (north) bounding coordinate
- **precision** (*int, optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns

window

Return type*Window***window_bounds(*window*)**

Get the bounds of a window

Parameters**window** (`rasterio.windows.Window`) – Dataset window**Returns****bounds** – x_min, y_min, x_max, y_max for the given window**Return type***tuple***window_transform(*window*)**

Get the affine transform for a dataset window.

Parameters**window** (`rasterio.windows.Window`) – Dataset window**Returns****transform** – The affine transform matrix for the given window**Return type***Affine***write(*arr*, *indexes=None*, *window=None*, *masked=False*)**

Write the arr array into indexed bands of the dataset.

If given a Numpy MaskedArray and masked is True, the input's data and mask will be written to the dataset's bands and band mask. If masked is False, no band mask is written. Instead, the input array's masked values are filled with the dataset's nodata value (if defined) or the input's own fill value.

Parameters

- **arr** (*array-like*) – This may be a numpy MaskedArray.
- **indexes** (*int* or *list*, *optional*) – Which bands of the dataset to write to. The default is all.
- **window** (*Window*, *optional*) – The region (slice) of the dataset to which arr will be written. The default is the entire dataset.
- **masked** (*bool*, *optional*) – Whether or not to write to the dataset's band mask.

Return type

None

Raises*RasterioIOError* – If the write fails.**write_band(*bidx*, *src*, *window=None*)**

Write the src array into the bidx band.

Band indexes begin with 1: read_band(1) returns the first band.

The optional *window* argument takes a tuple like:`((row_start, row_stop), (col_start, col_stop))`

specifying a raster subset to write into.

write_colormap(*bidx, colormap*)

Write a colormap for a band to the dataset.

A colormap maps pixel values of a single-band dataset to RGB or RGBA colors.

Parameters

- **bidx** (*int*) – Index of the band (starting with 1).
- **colormap** (*Mapping*) – Keys are integers and values are 3 or 4-tuples of ints.

Return type

None

write_mask(*mask_array, window=None*)

Write to the dataset's band mask.

Values > 0 represent valid data.

Parameters

- **mask_array** (*ndarray*) – Values of 0 represent invalid or missing data. Values > 0 represent valid data.
- **window** (*Window, optional*) – A subset of the dataset's band mask.

Return type

None

Raises

RasterioIOError – When no mask is written.

write_transform(*transform*)**xy**(*row, col, z=None, offset='center', transform_method=TransformMethod.affine, **rpc_options*)

Get the coordinates x, y of a pixel at row, col.

The pixel's center is returned by default, but a corner can be returned by setting *offset* to one of *ul*, *ur*, *ll*, *lr*.

Parameters

- **row** (*int*) – Pixel row.
- **col** (*int*) – Pixel column.
- **z** (*float, optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **offset** (*str, optional*) – Determines if the returned coordinates are for the center of the pixel or for a corner.
- **transform_method** (*TransformMethod, optional*) – The coordinate transformation method. Default: *TransformMethod.affine*.
- **rpc_options** (*dict, optional*) – Additional arguments passed to GDALCreateRPC-Transformer

Returns

x, y

Return type

tuple

class rasterio.io.DatasetReaderBases: `DatasetReaderBase`, `WindowMethodsMixin`, `TransformMethodsMixin`

An unbuffered data and metadata reader

block_shapes

An ordered list of block shapes for each bands

Shapes are tuples and have the same ordering as the dataset's shape: (count of image rows, count of image columns).

Return type`list`**block_size**(*bidx*, *i*, *j*)

Returns the size in bytes of a particular block

Only useful for TIFF formatted datasets.

Parameters

- **bidx** (`int`) – Band index, starting with 1.
- **i** (`int`) – Row index of the block, starting with 0.
- **j** (`int`) – Column index of the block, starting with 0.

Return type`int`**block_window**(*bidx*, *i*, *j*)

Returns the window for a particular block

Parameters

- **bidx** (`int`) – Band index, starting with 1.
- **i** (`int`) – Row index of the block, starting with 0.
- **j** (`int`) – Column index of the block, starting with 0.

Return type`Window`**block_windows**(*bidx*=0)

Iterator over a band's blocks and their windows

The primary use of this method is to obtain windows to pass to `read()` for highly efficient access to raster block data.The positional parameter *bidx* takes the index (starting at 1) of the desired band. This iterator yields blocks “left to right” and “top to bottom” and is similar to Python’s `enumerate()` in that the first element is the block index and the second is the dataset window.Blocks are built-in to a dataset and describe how pixels are grouped within each band and provide a mechanism for efficient I/O. A window is a range of pixels within a single band defined by row start, row stop, column start, and column stop. For example, `((0, 2), (0, 2))` defines a 2 x 2 window at the upper left corner of a raster band. Blocks are referenced by an `(i, j)` tuple where `(0, 0)` would be a band’s upper left block.

Raster I/O is performed at the block level, so accessing a window spanning multiple rows in a striped raster requires reading each row. Accessing a 2 x 2 window at the center of a 1800 x 3600 image requires reading 2 rows, or 7200 pixels just to get the target 4. The same image with internal 256 x 256 blocks

would require reading at least 1 block (if the window entire window falls within a single block) and at most 4 blocks, or at least 512 pixels and at most 2048.

Given an image that is 512 x 512 with blocks that are 256 x 256, its blocks and windows would look like:

Blocks:

| 0 | 256 | 512 |
|--------|--------------|-----|
| 0 | -----+-----+ | |
| | | |
| (0, 0) | (0, 1) | |
| | | |
| 256 | -----+-----+ | |
| | | |
| (1, 0) | (1, 1) | |
| | | |
| 512 | -----+-----+ | |

Windows:

```
UL: ((0, 256), (0, 256))
UR: ((0, 256), (256, 512))
LL: ((256, 512), (0, 256))
LR: ((256, 512), (256, 512))
```

Parameters

idx (*int*, *optional*) – The band index (using 1-based indexing) from which to extract windows. A value less than 1 uses the first band if all bands have homogeneous windows and raises an exception otherwise.

Yields

block, window

bounds

Returns the lower left and upper right bounds of the dataset in the units of its coordinate reference system.

The returned value is a tuple: (lower left x, lower left y, upper right x, upper right y)

checksum(bidx, window=None)

Compute an integer checksum for the stored band

Parameters

- **bidx** (*int*) – The band's index (1-indexed).
- **window** (*tuple*, *optional*) – A window of the band. Default is the entire extent of the band.

Return type

An int.

close()

Close the dataset and unwind attached exit stack.

closed

Test if the dataset is closed

Return type

bool

colorinterp

A sequence of ColorInterp.<enum> in band order.

Return type

tuple

colormap(bidx)

Returns a dict containing the colormap for a band.

Parameters**bidx** (int) – Index of the band whose colormap will be returned. Band index starts at 1.**Returns**

Mapping of color index value (starting at 0) to RGBA color as a 4-element tuple.

Return type

dict

Raises

- **ValueError** – If no colormap is found for the specified band (NULL color table).
- **IndexError** – If no band exists for the provided index.

compression**count**

The number of raster bands in the dataset

Return type

int

crs

The dataset's coordinate reference system

In setting this property, the value may be a CRS object or an EPSG:nnnn or WKT string.

Return type

CRS

dataset_mask(out=None, out_shape=None, window=None, boundless=False, resampling=Resampling.nearest)

Get the dataset's 2D valid data mask.

Parameters

- **out** (numpy ndarray, optional) – As with Numpy ufuncs, this is an optional reference to an output array with the same dimensions and shape into which data will be placed.

Note: the method's return value may be a view on this array. In other words, *out* is likely to be an incomplete representation of the method's results.

Cannot be combined with *out_shape*.

- **out_shape** (tuple, optional) – A tuple describing the output array's shape. Allows for decimated reads without constructing an output Numpy array.

Cannot be combined with *out*.

- **window** (a pair (`tuple`) of pairs of ints or `Window`, optional) – The optional `window` argument is a 2 item tuple. The first item is a tuple containing the indexes of the rows at which the window starts and stops and the second is a tuple containing the indexes of the columns at which the window starts and stops. For example, `((0, 2), (0, 2))` defines a 2x2 window at the upper left of the raster dataset.
- **boundless** (bool, optional (default `False`)) – If `True`, windows that extend beyond the dataset's extent are permitted and partially or completely filled arrays will be returned as appropriate.
- **resampling** (`Resampling`) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.

Returns

The dtype of this array is `uint8`. 0 = nodata, 255 = valid data.

Return type

Numpy ndarray or a view on a Numpy ndarray

Notes

Note: as with Numpy ufuncs, an object is returned even if you use the optional `out` argument and the return value shall be preferentially used by callers.

The dataset mask is calculated based on the individual band masks according to the following logic, in order of precedence:

1. If a `.msk` file, dataset-wide alpha, or internal mask exists it will be used for the dataset mask.
2. Else if the dataset is a 4-band with a shadow nodata value, band 4 will be used as the dataset mask.
3. If a nodata value exists, use the binary OR (`|`) of the band masks 4. If no nodata value exists, return a mask filled with 255.

Note that this differs from `read_masks` and GDAL RFC15 in that it applies per-dataset, not per-band (see https://trac.osgeo.org/gdal/wiki/rfc15_nodatabitmask)

descriptions

Descriptions for each dataset band

To set descriptions, one for each band is required.

Return type

`list of str`

driver**dtypes**

The data types of each band in index order

Return type

`list of str`

files

Returns a sequence of files associated with the dataset.

Return type

`tuple`

gcps

ground control points and their coordinate reference system.

This property is a 2-tuple, or pair: (gcps, crs).

gcps

[list of GroundControlPoint] Zero or more ground control points.

crs: CRS

The coordinate reference system of the ground control points.

get_gcps()

Get GCPs and their associated CRS.

get_nodatavals()**get_tag_item(ns, dm=None, bidx=0, ovr=None)**

Returns tag item value

Parameters

- **ns** (*str*) – The key for the metadata item to fetch.
- **dm** (*str*) – The domain to fetch for.
- **bidx** (*int*) – Band index, starting with 1.
- **ovr** (*int*) – Overview level

Return type

str

get_transform()

Returns a GDAL geotransform in its native form.

height**index(x, y, z=None, op=<built-in function floor>, precision=None, transform_method=TransformMethod.affine, **rpc_options)**

Get the (row, col) index of the pixel containing (x, y).

Parameters

- **x** (*float*) – x value in coordinate reference system
- **y** (*float*) – y value in coordinate reference system
- **z** (*float, optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **op** (*function, optional (default: math.floor)*) – Function to convert fractional pixels to whole numbers (floor, ceiling, round)
- **transform_method** (*TransformMethod, optional*) – The coordinate transformation method. Default: *TransformMethod.affine*.
- **rpc_options** (*dict, optional*) – Additional arguments passed to GDALCreateRPC-Transformer
- **precision** (*int, optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns

(row index, col index)

Return type`tuple`**indexes**

The 1-based indexes of each band in the dataset

For a 3-band dataset, this property will be [1, 2, 3].

Return type`list of int`**interleaving****is_tiled****lnglat()****mask_flagEnums**

Sets of flags describing the sources of band masks.

Parameters

- **all_valid** (*There are no invalid pixels, all mask values will be*) – 255. When used this will normally be the only flag set.
- **per_dataset** (*The mask band is shared between all bands on the*) – dataset.
- **alpha** (*The mask band is actually an alpha band and may have*) – values other than 0 and 255.
- **nodata** (*Indicates the mask is actually being generated from*) – nodata values (mutually exclusive of “alpha”).

Returns

One list of rasterio.enums.MaskFlags members per band.

Return type`list [, list*]`**Examples**

For a 3 band dataset that has masks derived from nodata values:

```
>>> dataset.mask_flagEnums
([<MaskFlags.nodata: 8>], [<MaskFlags.nodata: 8>], [<MaskFlags.nodata: 8>])
>>> band1_flags = dataset.mask_flagEnums[0]
>>> rasterio.enums.MaskFlags.nodata in band1_flags
True
>>> rasterio.enums.MaskFlags.alpha in band1_flags
False
```

meta

The basic metadata of this dataset.

mode**name****nodata**

The dataset’s single nodata value

Notes

May be set.

Return type

`float`

nodatavals

Nodata values for each band

Notes

This may not be set.

Return type

`list of float`

offsets

Raster offset for each dataset band

To set offsets, one for each band is required.

Return type

`list of float`

options**overviews(*bidx*)****photometric****profile**

Basic metadata and creation options of this dataset.

May be passed as keyword arguments to `rasterio.open()` to create a clone of this dataset.

read(*indexes=None, out=None, window=None, masked=False, out_shape=None, boundless=False, resampling=Resampling.nearest, fill_value=None, out_dtype=None*)

Read band data and, optionally, mask as an array.

A smaller (or larger) region of the dataset may be specified and it may be resampled and/or converted to a different data type.

Parameters

- **indexes (`int` or `list`, `optional`)** – If `indexes` is a list, the result is a 3D array, but is a 2D array if it is a band index number.
- **out (`numpy ndarray`, `optional`)** – As with Numpy ufuncs, this is an optional reference to an output array into which data will be placed. If the height and width of `out` differ from that of the specified window (see below), the raster image will be decimated or replicated using the specified resampling method (also see below). This parameter cannot be combined with `out_shape`.

Note: the method's return value may be a view on this array. In other words, `out` is likely to be an incomplete representation of the method's results.

- **out_dtype (`str` or `numpy dtype`)** – The desired output data type. For example: ‘`uint8`’ or `rasterio.uint16`.

- **out_shape** (`tuple`, *optional*) – A tuple describing the shape of a new output array. See `out` (above) for notes on image decimation and replication. This parameter cannot be combined with `out`.
- **window** (`Window`, *optional*) – The region (slice) of the dataset from which data will be read. The default is the entire dataset.
- **masked** (`bool`, *optional*) – If `masked` is *True* the return value will be a masked array. Otherwise (the default) the return value will be a regular array. Masks will be exactly the inverse of the GDAL RFC 15 conforming arrays returned by `read_masks()`.
- **boundless** (`bool`, optional (default *False*)) – If *True*, windows that extend beyond the dataset’s extent are permitted and partially or completely filled arrays will be returned as appropriate.
- **resampling** (`Resampling`) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.
- **fill_value** (`scalar`) – Fill value applied in the `boundless=True` case only. Like the `fill_value` of `numpy.ma.MaskedArray`, should be value valid for the dataset’s data type.

Return type

Numpy ndarray or a view on a Numpy ndarray

Raises

`RasterioIOError` – If the write fails.

Notes

This data is read from the dataset’s band cache, which means that repeated reads of the same windows may avoid I/O.

As with Numpy ufuncs, an object is returned even if you use the optional `out` argument and the return value shall be preferentially used by callers.

`read_crs()`

Return the GDAL dataset’s stored CRS

`read_masks(indexes=None, out=None, out_shape=None, window=None, boundless=False, resampling=Resampling.nearest)`

Read band masks as an array.

A smaller (or larger) region of the dataset may be specified and it may be resampled and/or converted to a different data type.

Parameters

- **indexes** (`int` or `list`, *optional*) – If `indexes` is a list, the result is a 3D array, but is a 2D array if it is a band index number.
- **out** (`numpy ndarray`, *optional*) – As with Numpy ufuncs, this is an optional reference to an output array into which data will be placed. If the height and width of `out` differ from that of the specified window (see below), the raster image will be decimated or replicated using the specified resampling method (also see below). This parameter cannot be combined with `out_shape`.

Note: the method’s return value may be a view on this array. In other words, `out` is likely to be an incomplete representation of the method’s results.

- **out_shape** (*tuple, optional*) – A tuple describing the shape of a new output array. See *out* (above) for notes on image decimation and replication. This parameter cannot be combined with *out*.
- **window** (*Window, optional*) – The region (slice) of the dataset from which data will be read. The default is the entire dataset.
- **boundless** (*bool, optional (default False)*) – If *True*, windows that extend beyond the dataset’s extent are permitted and partially or completely filled arrays will be returned as appropriate.
- **resampling** (*Resampling*) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.

Return type

Numpy ndarray or a view on a Numpy ndarray

Raises

RasterioIOError – If the write fails.

Notes

This data is read from the dataset’s band cache, which means that repeated reads of the same windows may avoid I/O.

As with Numpy ufuncs, an object is returned even if you use the optional *out* argument and the return value shall be preferentially used by callers.

read_transform()

Return the stored GDAL GeoTransform

res

Returns the (width, height) of pixels in the units of its coordinate reference system.

rpcs

Rational polynomial coefficients mapping between pixel and geodetic coordinates.

This property is a dict-like object.

rpcs : RPC instance containing coefficients. Empty if dataset does not have any metadata in the “RPC” domain.

sample(xy, indexes=None, masked=False)

Get the values of a dataset at certain positions

Values are from the nearest pixel. They are not interpolated.

Parameters

- **xy** (*iterable*) – Pairs of x, y coordinates (floats) in the dataset’s reference system.
- **indexes** (*int or list of int*) – Indexes of dataset bands to sample.
- **masked** (*bool, default: False*) – Whether to mask samples that fall outside the extent of the dataset.

Returns

Arrays of length equal to the number of specified indexes containing the dataset values for the bands corresponding to those indexes.

Return type
iterable

scales

Raster scale for each dataset band

To set scales, one for each band is required.

Return type
list of float

shape

start()

Start the dataset's life cycle

statistics(bidx, approx=False, clear_cache=False)

Get min, max, mean, and standard deviation of a raster band.

Parameters

- **bidx** (int) – The band's index (1-indexed).
- **approx** (bool, optional) – If True, statistics will be calculated from reduced resolution data.
- **clear_cache** (bool, optional) – If True, saved stats will be deleted and statistics will be recomputed. Requires GDAL version >= 3.2.

Return type

Statistics

Notes

GDAL will preferentially use statistics kept in raster metadata like images tags or an XML sidecar. If that metadata is out of date, the statistics may not correspond to the actual data.

Additionally, GDAL will save statistics to file metadata as a side effect if that metadata does not already exist.

stop()

Close the GDAL dataset handle

subdatasets

Sequence of subdatasets

tag_namespaces(bidx=0)

Get a list of the dataset's metadata domains.

Returned items may be passed as *ns* to the tags method.

Parameters

- **int(bidx)** – Can be used to select a specific band, otherwise the dataset's general metadata domains are returned.
- **optional** – Can be used to select a specific band, otherwise the dataset's general metadata domains are returned.

Return type

list of str

tags(*bidx=0, ns=None*)

Returns a dict containing copies of the dataset or band's tags.

Tags are pairs of key and value strings. Tags belong to namespaces. The standard namespaces are: default (None) and 'IMAGE_STRUCTURE'. Applications can create their own additional namespaces.

The optional bidx argument can be used to select the tags of a specific band. The optional ns argument can be used to select a namespace other than the default.

transform

The dataset's georeferencing transformation matrix

This transform maps pixel row/column coordinates to coordinates in the dataset's coordinate reference system.

Return type

Affine

units

one units string for each dataset band

Possible values include 'meters' or 'degC'. See the Pint project for a suggested list of units.

To set units, one for each band is required.

Return type

list of str

Type

A list of str

width**window**(*left, bottom, right, top, precision=None*)

Get the window corresponding to the bounding coordinates.

The resulting window is not cropped to the row and column limits of the dataset.

Parameters

- **left** (`float`) – Left (west) bounding coordinate
- **bottom** (`float`) – Bottom (south) bounding coordinate
- **right** (`float`) – Right (east) bounding coordinate
- **top** (`float`) – Top (north) bounding coordinate
- **precision** (`int`, *optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns

window

Return type

Window

window_bounds(*window*)

Get the bounds of a window

Parameters

window (`rasterio.windows.Window`) – Dataset window

Returns

bounds – x_min, y_min, x_max, y_max for the given window

Return type

tuple

window_transform(window)

Get the affine transform for a dataset window.

Parameters**window** (`rasterio.windows.Window`) – Dataset window**Returns****transform** – The affine transform matrix for the given window**Return type**

Affine

write_transform(value)**xy(row, col, z=None, offset='center', transform_method=TransformMethod.affine, **rpc_options)**

Get the coordinates x, y of a pixel at row, col.

The pixel's center is returned by default, but a corner can be returned by setting `offset` to one of `ul`, `ur`, `ll`, `lr`.**Parameters**

- **row** (`int`) – Pixel row.
- **col** (`int`) – Pixel column.
- **z** (`float, optional`) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **offset** (`str, optional`) – Determines if the returned coordinates are for the center of the pixel or for a corner.
- **transform_method** (`TransformMethod, optional`) – The coordinate transformation method. Default: `TransformMethod.affine`.
- **rpc_options** (`dict, optional`) – Additional arguments passed to GDALCreateRPC-Transformer

Returns

x, y

Return type

tuple

class rasterio.io.DatasetWriterBases: `DatasetWriterBase, WindowMethodsMixin, TransformMethodsMixin`

An unbuffered data and metadata writer. Its methods write data directly to disk.

block_shapes

An ordered list of block shapes for each bands

Shapes are tuples and have the same ordering as the dataset's shape: (count of image rows, count of image columns).

Return type

list

block_size(bidx, i, j)

Returns the size in bytes of a particular block

Only useful for TIFF formatted datasets.

Parameters

- **idx** (`int`) – Band index, starting with 1.
- **i** (`int`) – Row index of the block, starting with 0.
- **j** (`int`) – Column index of the block, starting with 0.

Return type`int`**block_window**(*idx*, *i*, *j*)

Returns the window for a particular block

Parameters

- **idx** (`int`) – Band index, starting with 1.
- **i** (`int`) – Row index of the block, starting with 0.
- **j** (`int`) – Column index of the block, starting with 0.

Return type`Window`**block_windows**(*idx*=0)

Iterator over a band's blocks and their windows


The primary use of this method is to obtain windows to pass to `read()` for highly efficient access to raster block data.

The positional parameter *idx* takes the index (starting at 1) of the desired band. This iterator yields blocks “left to right” and “top to bottom” and is similar to Python’s `enumerate()` in that the first element is the block index and the second is the dataset window.

Blocks are built-in to a dataset and describe how pixels are grouped within each band and provide a mechanism for efficient I/O. A window is a range of pixels within a single band defined by row start, row stop, column start, and column stop. For example, `((0, 2), (0, 2))` defines a 2 x 2 window at the upper left corner of a raster band. Blocks are referenced by an `(i, j)` tuple where `(0, 0)` would be a band’s upper left block.

Raster I/O is performed at the block level, so accessing a window spanning multiple rows in a striped raster requires reading each row. Accessing a 2 x 2 window at the center of a 1800 x 3600 image requires reading 2 rows, or 7200 pixels just to get the target 4. The same image with internal 256 x 256 blocks would require reading at least 1 block (if the window entire window falls within a single block) and at most 4 blocks, or at least 512 pixels and at most 2048.

Given an image that is 512 x 512 with blocks that are 256 x 256, its blocks and windows would look like:

Blocks:

(continues on next page)

(continued from previous page)

| |
|---|
| <pre>512 +-----+-----+ Windows: +-----+ UL: ((0, 256), (0, 256)) UR: ((0, 256), (256, 512)) LL: ((256, 512), (0, 256)) LR: ((256, 512), (256, 512))</pre> |
|---|

Parameters

idx (*int*, *optional*) – The band index (using 1-based indexing) from which to extract windows. A value less than 1 uses the first band if all bands have homogeneous windows and raises an exception otherwise.

Yields

block, window

bounds

Returns the lower left and upper right bounds of the dataset in the units of its coordinate reference system.

The returned value is a tuple: (lower left x, lower left y, upper right x, upper right y)

build_overviews(*factors*, *resampling=Resampling.nearest*)

Build overviews at one or more decimation factors for all bands of the dataset.

checksum(*idx*, *window=None*)

Compute an integer checksum for the stored band

Parameters

- **idx** (*int*) – The band's index (1-indexed).
- **window** (*tuple*, *optional*) – A window of the band. Default is the entire extent of the band.

Return type

An int.

close()

Close the dataset and unwind attached exit stack.

closed

Test if the dataset is closed

Return type

bool

colorinterp

A sequence of ColorInterp.<enum> in band order.

Return type

tuple

colormap(*idx*)

Returns a dict containing the colormap for a band.

Parameters

band_idx (`int`) – Index of the band whose colormap will be returned. Band index starts at 1.

Returns

Mapping of color index value (starting at 0) to RGBA color as a 4-element tuple.

Return type

`dict`

Raises

- `ValueError` – If no colormap is found for the specified band (NULL color table).
- `IndexError` – If no band exists for the provided index.

compression**count**

The number of raster bands in the dataset

Return type

`int`

crs

The dataset's coordinate reference system

In setting this property, the value may be a CRS object or an EPSG:nnnn or WKT string.

Return type

`CRS`

dataset_mask(*out=None*, *out_shape=None*, *window=None*, *boundless=False*,
resampling=Resampling.nearest)

Get the dataset's 2D valid data mask.

Parameters

- **out** (`numpy ndarray, optional`) – As with Numpy ufuncs, this is an optional reference to an output array with the same dimensions and shape into which data will be placed.

Note: the method's return value may be a view on this array. In other words, *out* is likely to be an incomplete representation of the method's results.

Cannot be combined with *out_shape*.

- **out_shape** (`tuple, optional`) – A tuple describing the output array's shape. Allows for decimated reads without constructing an output Numpy array.

Cannot be combined with *out*.

- **window** (*a pair (tuple) of pairs of ints or Window, optional*) – The optional *window* argument is a 2 item tuple. The first item is a tuple containing the indexes of the rows at which the window starts and stops and the second is a tuple containing the indexes of the columns at which the window starts and stops. For example, ((0, 2), (0, 2)) defines a 2x2 window at the upper left of the raster dataset.

- **boundless** (`bool, optional (default False)`) – If *True*, windows that extend beyond the dataset's extent are permitted and partially or completely filled arrays will be returned as appropriate.

- **resampling** (`Resampling`) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.

Returns

The dtype of this array is uint8. 0 = nodata, 255 = valid data.

Return type

Numpy ndarray or a view on a Numpy ndarray

Notes

Note: as with Numpy ufuncs, an object is returned even if you use the optional *out* argument and the return value shall be preferentially used by callers.

The dataset mask is calculated based on the individual band masks according to the following logic, in order of precedence:

1. If a .msk file, dataset-wide alpha, or internal mask exists it will be used for the dataset mask.
2. Else if the dataset is a 4-band with a shadow nodata value, band 4 will be used as the dataset mask.
3. If a nodata value exists, use the binary OR (|) of the band masks 4. If no nodata value exists, return a mask filled with 255.

Note that this differs from `read_masks` and GDAL RFC15 in that it applies per-dataset, not per-band (see https://trac.osgeo.org/gdal/wiki/rfc15_nodatabitmask)

descriptions

Descriptions for each dataset band

To set descriptions, one for each band is required.

Return type

list of str

driver**dtypes**

The data types of each band in index order

Return type

list of str

files

Returns a sequence of files associated with the dataset.

Return type

tuple

gcps

ground control points and their coordinate reference system.

This property is a 2-tuple, or pair: (gcps, crs).

gcps

[list of GroundControlPoint] Zero or more ground control points.

crs: CRS

The coordinate reference system of the ground control points.

get_gcps()

Get GCPs and their associated CRS.

get_nodatavals()

get_tag_item(*ns*, *dm*=*None*, *bidx*=0, *ovr*=*None*)

Returns tag item value

Parameters

- **ns** (*str*) – The key for the metadata item to fetch.
- **dm** (*str*) – The domain to fetch for.
- **bidx** (*int*) – Band index, starting with 1.
- **ovr** (*int*) – Overview level

Return type*str***get_transform()**

Returns a GDAL geotransform in its native form.

height**index**(*x*, *y*, *z*=*None*, *op*=<built-in function *floor*>, *precision*=*None*, *transform_method*=*TransformMethod.affine*, ***rpc_options*)

Get the (row, col) index of the pixel containing (x, y).

Parameters

- **x** (*float*) – x value in coordinate reference system
- **y** (*float*) – y value in coordinate reference system
- **z** (*float*, *optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **op** (*function*, *optional* (*default*: *math.floor*)) – Function to convert fractional pixels to whole numbers (floor, ceiling, round)
- **transform_method** (*TransformMethod*, *optional*) – The coordinate transformation method. Default: *TransformMethod.affine*.
- **rpc_options** (*dict*, *optional*) – Additional arguments passed to GDALCreateRPC-Transformer
- **precision** (*int*, *optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns

(row index, col index)

Return type*tuple***indexes**

The 1-based indexes of each band in the dataset

For a 3-band dataset, this property will be [1, 2, 3].

Return typelist of *int***interleaving****is_tiled**

lnglat()**mask_flagEnums**

Sets of flags describing the sources of band masks.

Parameters

- **all_valid** (*There are no invalid pixels, all mask values will be*) – 255. When used this will normally be the only flag set.
- **per_dataset** (*The mask band is shared between all bands on the*) – dataset.
- **alpha** (*The mask band is actually an alpha band and may have*) – values other than 0 and 255.
- **nodata** (*Indicates the mask is actually being generated from*) – nodata values (mutually exclusive of “alpha”).

Returns

One list of rasterio.enums.MaskFlags members per band.

Return type

`list [, list*]`

Examples

For a 3 band dataset that has masks derived from nodata values:

```
>>> dataset.mask_flagEnums
([<MaskFlags.nodata: 8>], [<MaskFlags.nodata: 8>], [<MaskFlags.nodata: 8>])
>>> band1_flags = dataset.mask_flagEnums[0]
>>> rasterio.enums.MaskFlags.nodata in band1_flags
True
>>> rasterio.enums.MaskFlags.alpha in band1_flags
False
```

meta

The basic metadata of this dataset.

mode**name****nodata**

The dataset’s single nodata value

Notes

May be set.

Return type

`float`

nodatavals

Nodata values for each band

Notes

This may not be set.

Return type

list of float

offsets

Raster offset for each dataset band

To set offsets, one for each band is required.

Return type

list of float

options

`overviews(bidx)`

`photometric`

`profile`

Basic metadata and creation options of this dataset.

May be passed as keyword arguments to `rasterio.open()` to create a clone of this dataset.

`read(indexes=None, out=None, window=None, masked=False, out_shape=None, boundless=False, resampling=Resampling.nearest, fill_value=None, out_dtype=None)`

Read band data and, optionally, mask as an array.

A smaller (or larger) region of the dataset may be specified and it may be resampled and/or converted to a different data type.

Parameters

- **indexes** (`int or list, optional`) – If `indexes` is a list, the result is a 3D array, but is a 2D array if it is a band index number.
- **out** (`numpy ndarray, optional`) – As with Numpy ufuncs, this is an optional reference to an output array into which data will be placed. If the height and width of `out` differ from that of the specified window (see below), the raster image will be decimated or replicated using the specified resampling method (also see below). This parameter cannot be combined with `out_shape`.
Note: the method's return value may be a view on this array. In other words, `out` is likely to be an incomplete representation of the method's results.
- **out_dtype** (`str or numpy dtype`) – The desired output data type. For example: ‘uint8’ or `rasterio.uint16`.
- **out_shape** (`tuple, optional`) – A tuple describing the shape of a new output array. See `out` (above) for notes on image decimation and replication. This parameter cannot be combined with `out`.
- **window** (`Window, optional`) – The region (slice) of the dataset from which data will be read. The default is the entire dataset.
- **masked** (`bool, optional`) – If `masked` is `True` the return value will be a masked array. Otherwise (the default) the return value will be a regular array. Masks will be exactly the inverse of the GDAL RFC 15 conforming arrays returned by `read_masks()`.

- **boundless** (bool, optional (default *False*)) – If *True*, windows that extend beyond the dataset’s extent are permitted and partially or completely filled arrays will be returned as appropriate.
- **resampling** ([Resampling](#)) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.
- **fill_value** ([scalar](#)) – Fill value applied in the *boundless=True* case only. Like the `fill_value` of `numpy.ma.MaskedArray`, should be value valid for the dataset’s data type.

Return type

Numpy ndarray or a view on a Numpy ndarray

Raises

[RasterioIOError](#) – If the write fails.

Notes

This data is read from the dataset’s band cache, which means that repeated reads of the same windows may avoid I/O.

As with Numpy ufuncs, an object is returned even if you use the optional `out` argument and the return value shall be preferentially used by callers.

read_crs()

Return the GDAL dataset’s stored CRS

read_masks(*indexes=None, out=None, out_shape=None, window=None, boundless=False, resampling=Resampling.nearest*)

Read band masks as an array.

A smaller (or larger) region of the dataset may be specified and it may be resampled and/or converted to a different data type.

Parameters

- **indexes** ([int](#) or [list](#), optional) – If *indexes* is a list, the result is a 3D array, but is a 2D array if it is a band index number.
- **out** ([numpy ndarray](#), optional) – As with Numpy ufuncs, this is an optional reference to an output array into which data will be placed. If the height and width of *out* differ from that of the specified window (see below), the raster image will be decimated or replicated using the specified resampling method (also see below). This parameter cannot be combined with *out_shape*.
- Note:* the method’s return value may be a view on this array. In other words, *out* is likely to be an incomplete representation of the method’s results.
- **out_shape** ([tuple](#), optional) – A tuple describing the shape of a new output array. See *out* (above) for notes on image decimation and replication. This parameter cannot be combined with *out*.
- **window** ([Window](#), optional) – The region (slice) of the dataset from which data will be read. The default is the entire dataset.
- **boundless** (bool, optional (default *False*)) – If *True*, windows that extend beyond the dataset’s extent are permitted and partially or completely filled arrays will be returned as appropriate.

- **resampling** ([Resampling](#)) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.

Return type

Numpy ndarray or a view on a Numpy ndarray

Raises

[*RasterioIOError*](#) – If the write fails.

Notes

This data is read from the dataset’s band cache, which means that repeated reads of the same windows may avoid I/O.

As with Numpy ufuncs, an object is returned even if you use the optional *out* argument and the return value shall be preferentially used by callers.

read_transform()

Return the stored GDAL GeoTransform

res

Returns the (width, height) of pixels in the units of its coordinate reference system.

rpcs

Rational polynomial coefficients mapping between pixel and geodetic coordinates.

This property is a dict-like object.

rpcs : RPC instance containing coefficients. Empty if dataset does not have any metadata in the “RPC” domain.

sample(xy, indexes=None, masked=False)

Get the values of a dataset at certain positions

Values are from the nearest pixel. They are not interpolated.

Parameters

- **xy** ([iterable](#)) – Pairs of x, y coordinates (floats) in the dataset’s reference system.
- **indexes** ([int](#) or [list of int](#)) – Indexes of dataset bands to sample.
- **masked** ([bool](#), [default: False](#)) – Whether to mask samples that fall outside the extent of the dataset.

Returns

Arrays of length equal to the number of specified indexes containing the dataset values for the bands corresponding to those indexes.

Return type

iterable

scales

Raster scale for each dataset band

To set scales, one for each band is required.

Return type

[list of float](#)

set_band_description(*bidx*, *value*)

Sets the description of a dataset band.

Parameters

- **bidx** (*int*) – Index of the band (starting with 1).
- **value** (*string*) – A description of the band.

Return type

None

set_band_unit(*bidx*, *value*)

Sets the unit of measure of a dataset band.

Parameters

- **bidx** (*int*) – Index of the band (starting with 1).
- **value** (*str*) – A label for the band’s unit of measure such as ‘meters’ or ‘degC’. See the Pint project for a suggested list of units.

Return type

None

shape**start()**

Start the dataset’s life cycle

statistics(*bidx*, *approx=False*, *clear_cache=False*)

Get min, max, mean, and standard deviation of a raster band.

Parameters

- **bidx** (*int*) – The band’s index (1-indexed).
- **approx** (*bool*, *optional*) – If True, statistics will be calculated from reduced resolution data.
- **clear_cache** (*bool*, *optional*) – If True, saved stats will be deleted and statistics will be recomputed. Requires GDAL version >= 3.2.

Return type

Statistics

Notes

GDAL will preferentially use statistics kept in raster metadata like images tags or an XML sidecar. If that metadata is out of date, the statistics may not correspond to the actual data.

Additionally, GDAL will save statistics to file metadata as a side effect if that metadata does not already exist.

stop()

Close the GDAL dataset handle

subdatasets

Sequence of subdatasets

tag_namespaces(bidx=0)

Get a list of the dataset's metadata domains.

Returned items may be passed as *ns* to the tags method.

Parameters

- **int (bidx)** – Can be used to select a specific band, otherwise the dataset's general metadata domains are returned.
- **optional** – Can be used to select a specific band, otherwise the dataset's general metadata domains are returned.

Return type

list of str

tags(bidx=0, ns=None)

Returns a dict containing copies of the dataset or band's tags.

Tags are pairs of key and value strings. Tags belong to namespaces. The standard namespaces are: default (None) and 'IMAGE_STRUCTURE'. Applications can create their own additional namespaces.

The optional bidx argument can be used to select the tags of a specific band. The optional ns argument can be used to select a namespace other than the default.

transform

The dataset's georeferencing transformation matrix

This transform maps pixel row/column coordinates to coordinates in the dataset's coordinate reference system.

Return type

Affine

units

one units string for each dataset band

Possible values include 'meters' or 'degC'. See the Pint project for a suggested list of units.

To set units, one for each band is required.

Return type

list of str

Type

A list of str

update_tags(bidx=0, ns=None, **kwargs)

Updates the tags of a dataset or one of its bands.

Tags are pairs of key and value strings. Tags belong to namespaces. The standard namespaces are: default (None) and 'IMAGE_STRUCTURE'. Applications can create their own additional namespaces.

The optional bidx argument can be used to select the dataset band. The optional ns argument can be used to select a namespace other than the default.

width**window(left, bottom, right, top, precision=None)**

Get the window corresponding to the bounding coordinates.

The resulting window is not cropped to the row and column limits of the dataset.

Parameters

- **left** (*float*) – Left (west) bounding coordinate
- **bottom** (*float*) – Bottom (south) bounding coordinate
- **right** (*float*) – Right (east) bounding coordinate
- **top** (*float*) – Top (north) bounding coordinate
- **precision** (*int*, *optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns
`window`

Return type
`Window`

`window_bounds(window)`

Get the bounds of a window

Parameters
`window` (`rasterio.windows.Window`) – Dataset window

Returns
`bounds` – x_min, y_min, x_max, y_max for the given window

Return type
`tuple`

`window_transform(window)`

Get the affine transform for a dataset window.

Parameters
`window` (`rasterio.windows.Window`) – Dataset window

Returns
`transform` – The affine transform matrix for the given window

Return type
`Affine`

`write(arr, indexes=None, window=None, masked=False)`

Write the arr array into indexed bands of the dataset.

If given a Numpy MaskedArray and masked is True, the input's data and mask will be written to the dataset's bands and band mask. If masked is False, no band mask is written. Instead, the input array's masked values are filled with the dataset's nodata value (if defined) or the input's own fill value.

Parameters

- **arr** (*array-like*) – This may be a numpy MaskedArray.
- **indexes** (*int* or *list*, *optional*) – Which bands of the dataset to write to. The default is all.
- **window** (`Window`, *optional*) – The region (slice) of the dataset to which arr will be written. The default is the entire dataset.
- **masked** (*bool*, *optional*) – Whether or not to write to the dataset's band mask.

Return type
`None`

Raises

`RasterioIOError` – If the write fails.

write_band(*bidx*, *src*, *window=None*)

Write the *src* array into the *bidx* band.

Band indexes begin with 1: `read_band(1)` returns the first band.

The optional *window* argument takes a tuple like:

`((row_start, row_stop), (col_start, col_stop))`

specifying a raster subset to write into.

write_colormap(*bidx*, *colormap*)

Write a colormap for a band to the dataset.

A colormap maps pixel values of a single-band dataset to RGB or RGBA colors.

Parameters

- **bidx** (`int`) – Index of the band (starting with 1).
- **colormap** (`Mapping`) – Keys are integers and values are 3 or 4-tuples of ints.

Return type

`None`

write_mask(*mask_array*, *window=None*)

Write to the dataset's band mask.

Values > 0 represent valid data.

Parameters

- **mask_array** (`ndarray`) – Values of 0 represent invalid or missing data. Values > 0 represent valid data.
- **window** (`Window`, *optional*) – A subset of the dataset's band mask.

Return type

`None`

Raises

`RasterioIOError` – When no mask is written.

write_transform(*transform*)**xy**(*row*, *col*, *z=None*, *offset='center'*, *transform_method=TransformMethod.affine*, ***rpc_options*)

Get the coordinates x, y of a pixel at row, col.

The pixel's center is returned by default, but a corner can be returned by setting *offset* to one of *ul*, *ur*, *ll*, *lr*.

Parameters

- **row** (`int`) – Pixel row.
- **col** (`int`) – Pixel column.
- **z** (`float`, *optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **offset** (`str`, *optional*) – Determines if the returned coordinates are for the center of the pixel or for a corner.
- **transform_method** (`TransformMethod`, *optional*) – The coordinate transformation method. Default: `TransformMethod.affine`.

- **rpc_options** (*dict*, *optional*) – Additional arguments passed to GDALCreateRPC-Transformer

Returns

x, y

Return type

tuple

rasterio.io.FilePathalias of `_FilePath`**class rasterio.io.MemoryFile(file_or_bytes=None, dirname=None, filename=None, ext='.tif')**Bases: `MemoryFileBase`

A BytesIO-like object, backed by an in-memory file.

This allows formatted files to be read and written without I/O.

A `MemoryFile` created with initial bytes becomes immutable. A `MemoryFile` created without initial bytes may be written to using either file-like or dataset interfaces.**Examples**

A GeoTIFF can be loaded in memory and accessed using the GeoTIFF format driver

```
>>> with open('tests/data/RGB.byte.tif', 'rb') as f, MemoryFile(f) as memfile:
...     with memfile.open() as src:
...         pprint.pprint(src.profile)
...
{'count': 3,
 'crs': CRS({'init': 'epsg:32618'}),
 'driver': 'GTiff',
 'dtype': 'uint8',
 'height': 718,
 'interleave': 'pixel',
 'nodata': 0.0,
 'tiled': False,
 'transform': Affine(300.0379266750948, 0.0, 101985.0,
                    0.0, -300.041782729805, 2826915.0),
 'width': 791}
```

close()**exists()**

Test if the in-memory file exists.

Returns

True if the in-memory file exists.

Return type

bool

getbuffer()

Return a view on bytes of the file.

open(*driver=None*, *width=None*, *height=None*, *count=None*, *crs=None*, *transform=None*, *dtype=None*, *nodata=None*, *sharing=False*, ***kwargs*)

Open the file and return a Rasterio dataset object.

If data has already been written, the file is opened in ‘r’ mode. Otherwise, the file is opened in ‘w’ mode.

Parameters

- **parameter** (*Note well that there is no path*) –
- **a** (*contains a single dataset and there is no need to specify*) –
- **path**. –
- **the** (*Other parameters are optional and have the same semantics as*) –
- **rasterio.open()**. (*parameters of*) –

read(*size=-1*)

Read bytes from MemoryFile.

Parameters

size (*int*) – Number of bytes to read. Default is -1 (all bytes).

Returns

String of bytes read.

Return type

bytes

seek(*offset*, *whence=0*)

tell()

write(*data*)

Write data bytes to MemoryFile.

Parameters

data (*bytes*) –

Returns

Number of bytes written.

Return type

int

class rasterio.io.ZipMemoryFile(*file_or_bytes=None*)

Bases: *MemoryFile*

A read-only BytesIO-like object backed by an in-memory zip file.

This allows a zip file containing formatted files to be read without I/O.

close()

exists()

Test if the in-memory file exists.

Returns

True if the in-memory file exists.

Return type

bool

getbuffer()

Return a view on bytes of the file.

open(path, driver=None, sharing=False, **kwargs)

Open a dataset within the zipped stream.

Parameters

- **path** (`str`) – Path to a dataset in the zip file, relative to the root of the archive.
- **the** (*Other parameters are optional and have the same semantics as*) –
- **rasterio.open()**. (*parameters of*) –

Return type

A Rasterio dataset object

read(size=-1)

Read bytes from MemoryFile.

Parameters

size (`int`) – Number of bytes to read. Default is -1 (all bytes).

Returns

String of bytes read.

Return type

`bytes`

seek(offset, whence=0)**tell()****write(data)**

Write data bytes to MemoryFile.

Parameters

data (`bytes`) –

Returns

Number of bytes written.

Return type

`int`

rasterio.io.get_writer_for_driver(driver)

Return the writer class appropriate for the specified driver.

rasterio.io.get_writer_for_path(path, driver=None)

Return the writer class appropriate for the existing dataset.

rasterio.mask module

Mask the area outside of the input shapes with no data.

```
rasterio.mask.mask(dataset, shapes, all_touched=False, invert=False, nodata=None, filled=True, crop=False, pad=False, pad_width=0.5, indexes=None)
```

Creates a masked or filled array using input shapes. Pixels are masked or set to nodata outside the input shapes, unless *invert* is *True*.

If shapes do not overlap the raster and *crop=True*, a *ValueError* is raised. Otherwise, a warning is raised.

Parameters

- **dataset** (*a dataset object opened in 'r' mode*) – Raster to which the mask will be applied.
- **shapes** (*iterable object*) – The values must be a GeoJSON-like dict or an object that implements the Python geo interface protocol (such as a Shapely Polygon).
- **all_touched** (*bool (opt)*) – Include a pixel in the mask if it touches any of the shapes. If *False* (default), include a pixel only if its center is within one of the shapes, or if it is selected by Bresenham's line algorithm.
- **invert** (*bool (opt)*) – If *False* (default) pixels outside shapes will be masked. If *True*, pixels inside shape will be masked.
- **nodata** (*int or float (opt)*) – Value representing nodata within each raster band. If not set, defaults to the nodata value for the input raster. If there is no set nodata value for the raster, it defaults to 0.
- **filled** (*bool (opt)*) – If *True*, the pixels outside the features will be set to nodata. If *False*, the output array will contain the original pixel data, and only the mask will be based on shapes. Defaults to *True*.
- **crop** (*bool (opt)*) – Whether to crop the raster to the extent of the shapes. Defaults to *False*.
- **pad** (*bool (opt)*) – If *True*, the features will be padded in each direction by one half of a pixel prior to cropping raster. Defaults to *False*.
- **indexes** (*list of ints or a single int (opt)*) – If *indexes* is a list, the result is a 3D array, but is a 2D array if it is a band index number.

Returns

Two elements:

masked

[numpy ndarray or numpy.ma.MaskedArray] Data contained in the raster after applying the mask. If *filled* is *True* and *invert* is *False*, the return will be an array where pixels outside shapes are set to the nodata value (or nodata inside shapes if *invert* is *True*).

If *filled* is *False*, the return will be a MaskedArray in which pixels outside shapes are *True* (or *False* if *invert* is *True*).

out_transform

[affine.Affine()] Information for mapping pixel coordinates in *masked* to another coordinate system.

Return type

tuple

```
rasterio.mask.raster_geometry_mask(dataset, shapes, all_touched=False, invert=False, crop=False,
                                    pad=False, pad_width=0.5)
```

Create a mask from shapes, transform, and optional window within original raster.

By default, mask is intended for use as a numpy mask, where pixels that overlap shapes are False.

If shapes do not overlap the raster and crop=True, a ValueError is raised. Otherwise, a warning is raised, and a completely True mask is returned (if invert is False).

Parameters

- **dataset** (*a dataset object opened in 'r' mode*) – Raster for which the mask will be created.
- **shapes** (*iterable object*) – The values must be a GeoJSON-like dict or an object that implements the Python geo interface protocol (such as a Shapely Polygon).
- **all_touched** (*bool (opt)*) – Include a pixel in the mask if it touches any of the shapes. If False (default), include a pixel only if its center is within one of the shapes, or if it is selected by Bresenham's line algorithm.
- **invert** (*bool (opt)*) – If False (default), mask will be *False* inside shapes and *True* outside. If True, mask will be *True* inside shapes and *False* outside.
- **crop** (*bool (opt)*) – Whether to crop the dataset to the extent of the shapes. Defaults to False.
- **pad** (*bool (opt)*) – If True, the features will be padded in each direction by one half of a pixel prior to cropping dataset. Defaults to False.
- **pad_width** (*float (opt)*) – If pad is set (to maintain back-compatibility), then this will be the pixel-size width of the padding around the mask.

Returns

Three elements:

mask

[numpy ndarray of type ‘bool’] Mask that is *True* outside shapes, and *False* within shapes.

out_transform

[affine.Affine()] Information for mapping pixel coordinates in *masked* to another coordinate system.

window: rasterio.windows.Window instance

Window within original raster covered by shapes. None if crop is False.

Return type

tuple

rasterio.merge module

Copy valid pixels from input files to an output file.

```
rasterio.merge.copy_count(merged_data, new_data, merged_mask, new_mask, **kwargs)
```

Returns the count of valid pixels.

```
rasterio.merge.copy_first(merged_data, new_data, merged_mask, new_mask, **kwargs)
```

Returns the first available pixel.

`rasterio.merge.copy_last(merged_data, new_data, merged_mask, new_mask, **kwargs)`

Returns the last available pixel.

`rasterio.merge.copy_max(merged_data, new_data, merged_mask, new_mask, **kwargs)`

Returns the maximum value pixel.

`rasterio.merge.copy_min(merged_data, new_data, merged_mask, new_mask, **kwargs)`

Returns the minimum value pixel.

`rasterio.merge.copy_sum(merged_data, new_data, merged_mask, new_mask, **kwargs)`

Returns the sum of all pixel values.

`rasterio.merge.merge(datasets, bounds=None, res=None, nodata=None, dtype=None, precision=None, indexes=None, output_count=None, resampling=Resampling.nearest, method='first', target_aligned_pixels=False, dst_path=None, dst_kwds=None)`

Copy valid pixels from input files to an output file.

All files must have the same number of bands, data type, and coordinate reference system. Rotated rasters cannot be merged.

Input files are merged in their listed order using the reverse painter's algorithm (default) or another method. If the output file exists, its values will be overwritten by input values.

Geospatial bounds and resolution of a new output file in the units of the input file coordinate reference system may be provided and are otherwise taken from the first input file.

Parameters

- **datasets** (*list of dataset objects opened in 'r' mode, filenames or PathLike objects*) – source datasets to be merged.
- **bounds** (*tuple*, *optional*) – Bounds of the output image (left, bottom, right, top). If not set, bounds are determined from bounds of input rasters.
- **res** (*tuple*, *optional*) – Output resolution in units of coordinate reference system. If not set, the resolution of the first raster is used. If a single value is passed, output pixels will be square.
- **nodata** (*float*, *optional*) – nodata value to use in output file. If not set, uses the nodata value in the first input raster.
- **dtype** (*numpy dtype or string*) – dtype to use in outputfile. If not set, uses the dtype value in the first input raster.
- **precision** (*int*, *optional*) – This parameters is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.
- **indexes** (*list of ints or a single int, optional*) – bands to read and merge
- **output_count** (*int*, *optional*) – If using callable it may be useful to have additional bands in the output in addition to the indexes specified for read
- **resampling** (*Resampling*, *optional*) – Resampling algorithm used when reading input files. Default: *Resampling.nearest*.
- **method** (*str or callable*) –
pre-defined method:
first: reverse painting last: paint valid new on top of existing min: pixel-wise min of existing and new max: pixel-wise max of existing and new
or custom callable with signature:

merged_data
[array_like] array to update with new_data

new_data
[array_like] data to merge same shape as merged_data

merged_mask, new_mask
[array_like] boolean masks where merged/new data pixels are invalid same shape as merged_data

index: int
index of the current dataset within the merged dataset collection

roff: int
row offset in base array

coff: int
column offset in base array

- **target_aligned_pixels (bool, optional)** – Whether to adjust output image bounds so that pixel coordinates are integer multiples of pixel size, matching the `-tap` options of GDAL utilities. Default: False.
- **dst_path (str or PathLike, optional)** – Path of output dataset
- **dst_kwds (dict, optional)** – Dictionary of creation options and other parameters that will be overlaid on the profile of the output dataset.

Returns

Two elements:

dest: numpy ndarray

Contents of all input rasters in single array

out_transform: affine.Affine()

Information for mapping pixel coordinates in *dest* to another coordinate system

Return type

tuple

rasterio.path module

Dataset paths, identifiers, and filenames

Note well: this module is deprecated in 1.3.0 and will be removed in a future version.

rasterio.plot module

Implementations of various common operations.

Including `show()` for displaying an array or with matplotlib. Most can handle a numpy array or `rasterio.Band()`. Primarily supports \$ rio insp.

`rasterio.plot.adjust_band(band, kind=None)`

Adjust a band to be between 0 and 1.

Parameters

- **band (array, shape (height, width))** – A band of a raster object.
- **kind (str)** – An unused option. For now, there is only one option ('linear').

Returns

band_normed – An adjusted version of the input band.

Return type

array, shape (height, width)

rasterio.plot.get_plt()

import matplotlib.pyplot raise import error if matplotlib is not installed

rasterio.plot.plotting_extent(source, transform=None)**Returns an extent in the format needed**

for matplotlib's imshow (left, right, bottom, top) instead of rasterio's bounds (left, bottom, right, top)

Parameters

- **source** (*array or dataset object opened in 'r' mode*) – If array, data in the order rows, columns and optionally bands. If array is band order (bands in the first dimension), use arr[0]
- **transform** (*Affine, required if source is array*) – Defines the affine transform if source is an array

Returns

left, right, bottom, top

Return type

tuple of float

rasterio.plot.reshape_as_image(arr)

Returns the source array reshaped into the order expected by image processing and visualization software (matplotlib, scikit-image, etc) by swapping the axes order from (bands, rows, columns) to (rows, columns, bands)

Parameters

arr (*array-like of shape (bands, rows, columns)*) – image to reshape

rasterio.plot.reshape_as_raster(arr)

Returns the array in a raster order by swapping the axes order from (rows, columns, bands) to (bands, rows, columns)

Parameters

arr (*array-like in the image form of (rows, columns, bands)*) – image to reshape

rasterio.plot.show(source, with_bounds=True, contour=False, contour_label_kws=None, ax=None, title=None, transform=None, adjust=False, **kwargs)

Display a raster or raster band using matplotlib.

Parameters

- **source** (*array or dataset object opened in 'r' mode or Band or tuple(dataset, bidx)*) – If Band or tuple (dataset, bidx), display the selected band. If raster dataset display the rgb image as defined in the colorinterp metadata, or default to first band.
- **with_bounds** (*bool (opt)*) – Whether to change the image extent to the spatial bounds of the image, rather than pixel coordinates. Only works when source is (raster dataset, bidx) or raster dataset.
- **contour** (*bool (opt)*) – Whether to plot the raster data as contours

- **contour_label_kws** (*dictionary (opt)*) – Keyword arguments for labeling the contours, empty dictionary for no labels.
- **ax** (*matplotlib axes (opt)*) – Axes to plot on, otherwise uses current axes.
- **title** (*str, optional*) – Title for the figure.
- **transform** (*Affine, optional*) – Defines the affine transform if source is an array
- **adjust** (*bool*) – If the plotted data is an RGB image, adjust the values of each band so that they fall between 0 and 1 before plotting. If True, values will be adjusted by the min / max of each band. If False, no adjustment will be applied.
- ****kwargs** (*key, value pairings optional*) – These will be passed to the matplotlib imshow or contour method depending on contour argument. See full lists at: https://matplotlib.org/stable/api/_as_gen/matplotlib.pyplot.imshow.html or https://matplotlib.org/stable/api/_as_gen/matplotlib.pyplot.contour.html

Returns

ax – Axes with plot.

Return type

matplotlib Axes

`rasterio.plot.show_hist(source, bins=10, masked=True, title='Histogram', ax=None, label=None, **kwargs)`

Easily display a histogram with matplotlib.

Parameters

- **source** (*array or dataset object opened in 'r' mode or Band or tuple(dataset, bidx)*) – Input data to display. The first three arrays in multi-dimensional arrays are plotted as red, green, and blue.
- **bins** (*int, optional*) – Compute histogram across N bins.
- **masked** (*bool, optional*) – When working with a *rasterio.Band()* object, specifies if the data should be masked on read.
- **title** (*str, optional*) – Title for the figure.
- **ax** (*matplotlib axes (opt)*) – The raster will be added to this axes if passed.
- **label** (*matplotlib labels (opt)*) – If passed, matplotlib will use this label list. Otherwise, a default label list will be automatically created
- ****kwargs** (*optional keyword arguments*) – These will be passed to the matplotlib hist method. See full list at: http://matplotlib.org/api/axes_api.html?highlight=imshow#matplotlib.axes.Axes.hist

rasterio.profiles module

Raster dataset profiles.

`class rasterio.profiles.DefaultGTiffProfile(data={}, **kwds)`

Bases: *Profile*

Tiled, band-interleaved, LZW-compressed, 8-bit GTiff.

```
defaults = {'blockxsize': 256, 'blockysize': 256, 'compress': 'lzw', 'driver': 'GTiff', 'dtype': 'uint8', 'interleave': 'band', 'nodata': 0, 'tiled': True}
```

```
class rasterio.profiles.Profile(data={}, **kwds)
```

Bases: `UserDict`

Base class for Rasterio dataset profiles.

Subclasses will declare driver-specific creation options.

```
defaults = {}
```

rasterio.rpc module

```
class rasterio.rpc.RPC(height_off, height_scale, lat_off, lat_scale, line_den_coeff, line_num_coeff, line_off,
                       line_scale, long_off, long_scale, samp_den_coeff, samp_num_coeff, samp_off,
                       samp_scale, err_bias=None, err_rand=None)
```

Bases: `object`

Rational Polynomial Coefficients used to map (x, y, z) <-> (row, col) coordinates.

This class contains a mapping between various RPC attributes and values.

err_bias, err_rand

The RMS bias and random error in meters per horizontal axis of all points in image.

Type

`float`, optional

lat_off, long_off, height_off

Geodetic latitude, longitude, and height offset.

Type

`float`

lat_scale, long_scale, height_scale

Geodetic latitude, longitude, and height scaling.

Type

`float`

line_off, samp_off

Line (row) and sample (column) offset.

Type

`float`

line_scale, samp_scale

Line (row) and sample (column) offset.

Type

`float`

line_num_coeff, line_den_coeff, samp_num_coeff, samp_den_coeff

The twenty coefficients describing a numerator or denominator polynomial corresponding to line (row) or sample (col).

Type

`list`

err_bias

err_rand

classmethod from_gdal(*rpcs*)

Deserialize dict values to float or list.

Return type
RPC

height_off

height_scale

lat_off

lat_scale

line_den_coeff

line_num_coeff

line_off

line_scale

long_off

long_scale

samp_den_coeff

samp_num_coeff

samp_off

samp_scale

to_dict()

Return a dictionary representation of RPC

to_gdal()

Serialize RPC attribute name and values in a form expected by GDAL.

Return type
dict

Notes

The *err_bias* and *err_rand* are optional, and are not written to datasets by GDAL.

rasterio.sample module

rasterio.sample.sample_gen(*dataset*, *xy*, *indexes=None*, *masked=False*)

Sample pixels from a dataset

Parameters

- **dataset** (*rasterio Dataset*) – Opened in “r” mode.
- **xy** (*iterable*) – Pairs of x, y coordinates in the dataset’s reference system.

- **indexes** (*int or list of int*) – Indexes of dataset bands to sample.
- **masked** (*bool, default: False*) – Whether to mask samples that fall outside the extent of the dataset.

Yields

array – A array of length equal to the number of specified indexes containing the dataset values for the bands corresponding to those indexes.

rasterio.session module

Abstraction for sessions in various clouds.

```
class rasterio.session.AWSsession(session=None, aws_unsigned=None, aws_access_key_id=None,
                                   aws_secret_access_key=None, aws_session_token=None,
                                   region_name=None, profile_name=None, endpoint_url=None,
                                   requester_pays=False)
```

Bases: *Session*

Configures access to secured resources stored in AWS S3.

```
static aws_or_dummy(*args, **kwargs)
```

Create an AWSsession if boto3 is available, else DummySession

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type

Session

```
static cls_from_path(path)
```

Find the session class suited to the data at *path*.

Parameters

path (*str*) – A dataset path or identifier.

Return type

class

property credentials

The session credentials as a dict

```
static from_environ(*args, **kwargs)
```

Create a session object suited to the environment.

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type

Session

static from_foreign_session(session, cls=None)

Create a session object matching the foreign *session*.

Parameters

- **session** (*obj*) – A foreign session object.
- **cls** (*Session class, optional*) – The class to return.

Return type

Session

static from_path(path, *args, **kwargs)

Create a session object suited to the data at *path*.

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type

Session

get_credential_options()

Get credentials as GDAL configuration options

Return type

dict

classmethod hascreds(config)

Determine if the given configuration has proper credentials

Parameters

- **cls** (*class*) – A Session class.
- **config** (*dict*) – GDAL configuration as a dict.

Return type

bool

class rasterio.session.AzureSession(azure_storage_connection_string=None, azure_storage_account=None, azure_storage_access_key=None, azure_unsigned=False)

Bases: *Session*

Configures access to secured resources stored in Microsoft Azure Blob Storage.

static aws_or_dummy(*args, **kwargs)

Create an AWSSession if boto3 is available, else DummySession

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type

Session

static `cls_from_path(path)`

Find the session class suited to the data at *path*.

Parameters

- **path** (`str`) – A dataset path or identifier.

Return type

`class`

property `credentials`

The session credentials as a dict

static `from_environ(*args, **kwargs)`

Create a session object suited to the environment.

Parameters

- **path** (`str`) – A dataset path or identifier.
- **args** (`sequence`) – Positional arguments for the foreign session constructor.
- **kwargs** (`dict`) – Keyword arguments for the foreign session constructor.

Return type

`Session`

static `from_foreign_session(session, cls=None)`

Create a session object matching the foreign *session*.

Parameters

- **session** (`obj`) – A foreign session object.
- **cls** (`Session class, optional`) – The class to return.

Return type

`Session`

static `from_path(path, *args, **kwargs)`

Create a session object suited to the data at *path*.

Parameters

- **path** (`str`) – A dataset path or identifier.
- **args** (`sequence`) – Positional arguments for the foreign session constructor.
- **kwargs** (`dict`) – Keyword arguments for the foreign session constructor.

Return type

`Session`

`get_credential_options()`

Get credentials as GDAL configuration options

Return type

`dict`

`classmethod hascreds(config)`

Determine if the given configuration has proper credentials

Parameters

- **cls** (`class`) – A Session class.

- **config** (`dict`) – GDAL configuration as a dict.

Return type`bool`**class rasterio.session.DummySession(*args, **kwargs)**Bases: `Session`

A dummy session.

credentials

The session credentials.

Type`dict`**static aws_or_dummy(*args, **kwargs)**

Create an AWSSession if boto3 is available, else DummySession

Parameters

- **path** (`str`) – A dataset path or identifier.
- **args** (`sequence`) – Positional arguments for the foreign session constructor.
- **kwarg**s (`dict`) – Keyword arguments for the foreign session constructor.

Return type`Session`**static cls_from_path(path)**Find the session class suited to the data at `path`.**Parameters**`path` (`str`) – A dataset path or identifier.**Return type**`class`**static from_environ(*args, **kwargs)**

Create a session object suited to the environment.

Parameters

- **path** (`str`) – A dataset path or identifier.
- **args** (`sequence`) – Positional arguments for the foreign session constructor.
- **kwarg**s (`dict`) – Keyword arguments for the foreign session constructor.

Return type`Session`**static from_foreign_session(session, cls=None)**Create a session object matching the foreign `session`.**Parameters**

- **session** (`obj`) – A foreign session object.
- **cls** (`Session class, optional`) – The class to return.

Return type`Session`

static from_path(path, *args, **kwargs)Create a session object suited to the data at *path*.**Parameters**

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***get_credential_options()**

Get credentials as GDAL configuration options

Return type*dict***classmethod hascreds(config)**

Determine if the given configuration has proper credentials

Parameters

- **cls** (*class*) – A Session class.
- **config** (*dict*) – GDAL configuration as a dict.

Return type*bool***class rasterio.session.GSSession(google_application_credentials=None)**Bases: *Session*

Configures access to secured resources stored in Google Cloud Storage

static aws_or_dummy(*args, **kwargs)

Create an AWSSession if boto3 is available, else DummySession

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***static cls_from_path(path)**Find the session class suited to the data at *path*.**Parameters****path** (*str*) – A dataset path or identifier.**Return type***class***property credentials**

The session credentials as a dict

static from_environ(*args, **kwargs)

Create a session object suited to the environment.

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type

Session

static from_foreign_session(session, cls=None)

Create a session object matching the foreign *session*.

Parameters

- **session** (*obj*) – A foreign session object.
- **cls** (*Session class, optional*) – The class to return.

Return type

Session

static from_path(path, *args, **kwargs)

Create a session object suited to the data at *path*.

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type

Session

get_credential_options()

Get credentials as GDAL configuration options

Return type

dict

classmethod hascreds(config)

Determine if the given configuration has proper credentials

Parameters

- **cls** (*class*) – A Session class.
- **config** (*dict*) – GDAL configuration as a dict.

Return type

bool

class rasterio.session.OSSSession(oss_access_key_id=None, oss_secret_access_key=None, oss_endpoint=None)

Bases: *Session*

Configures access to secured resources stored in Alibaba Cloud OSS.

static aws_or_dummy(*args, **kwargs)

Create an AWSSession if boto3 is available, else DummySession

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***static cls_from_path(path)**Find the session class suited to the data at *path*.**Parameters**

- **path** (*str*) – A dataset path or identifier.

Return type

class

property credentials

The session credentials as a dict

static from_environ(*args, **kwargs)

Create a session object suited to the environment.

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***static from_foreign_session(session, cls=None)**Create a session object matching the foreign *session*.**Parameters**

- **session** (*obj*) – A foreign session object.
- **cls** (*Session class, optional*) – The class to return.

Return type*Session***static from_path(path, *args, **kwargs)**Create a session object suited to the data at *path*.**Parameters**

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session*

get_credential_options()

Get credentials as GDAL configuration options

Return type

`dict`

classmethod hascreds(config)

Determine if the given configuration has proper credentials

Parameters

- **cls** (`class`) – A Session class.
- **config** (`dict`) – GDAL configuration as a dict.

Return type

`bool`

class rasterio.session.Session

Bases: `object`

Base for classes that configure access to secured resources.

credentials

Keys and values for session credentials.

Type

`dict`

Notes

This class is not intended to be instantiated.

static aws_or_dummy(*args, **kwargs)

Create an AWSSession if boto3 is available, else DummySession

Parameters

- **path** (`str`) – A dataset path or identifier.
- **args** (`sequence`) – Positional arguments for the foreign session constructor.
- **kwargs** (`dict`) – Keyword arguments for the foreign session constructor.

Return type

`Session`

static cls_from_path(path)

Find the session class suited to the data at `path`.

Parameters

path (`str`) – A dataset path or identifier.

Return type

`class`

static from_environ(*args, **kwargs)

Create a session object suited to the environment.

Parameters

- **path** (`str`) – A dataset path or identifier.

- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***static from_foreign_session(session, cls=None)**Create a session object matching the foreign *session*.**Parameters**

- **session** (*obj*) – A foreign session object.
- **cls** (*Session class, optional*) – The class to return.

Return type*Session***static from_path(path, *args, **kwargs)**Create a session object suited to the data at *path*.**Parameters**

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwargs** (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***get_credential_options()**

Get credentials as GDAL configuration options

Return type*dict***classmethod hascreds(config)**

Determine if the given configuration has proper credentials

Parameters

- **cls** (*class*) – A Session class.
- **config** (*dict*) – GDAL configuration as a dict.

Return type*bool***class rasterio.session.SwiftSession(session=None, swift_storage_url=None, swift_auth_token=None, swift_auth_v1_url=None, swift_user=None, swift_key=None)**Bases: *Session*

Configures access to secured resources stored in OpenStack Swift Object Storage.

static aws_or_dummy(*args, **kwargs)

Create an AWSSession if boto3 is available, else DummySession

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.

- **kwarg**s (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***static** `cls_from_path(path)`Find the session class suited to the data at *path*.**Parameters****path** (*str*) – A dataset path or identifier.**Return type**

class

property `credentials`

The session credentials as a dict

static `from_environ(*args, **kwargs)`

Create a session object suited to the environment.

Parameters

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwarg**s (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***static** `from_foreign_session(session, cls=None)`Create a session object matching the foreign *session*.**Parameters**

- **session** (*obj*) – A foreign session object.
- **cls** (*Session class, optional*) – The class to return.

Return type*Session***static** `from_path(path, *args, **kwargs)`Create a session object suited to the data at *path*.**Parameters**

- **path** (*str*) – A dataset path or identifier.
- **args** (*sequence*) – Positional arguments for the foreign session constructor.
- **kwarg**s (*dict*) – Keyword arguments for the foreign session constructor.

Return type*Session***get_credential_options()**

Get credentials as GDAL configuration options :rtype: dict

classmethod `hascreds(config)`

Determine if the given configuration has proper credentials :param cls: A Session class. :type cls: class :param config: GDAL configuration as a dict. :type config: dict

Return type`bool``rasterio.session.parse_bool(v)`

CPLTestBool equivalent

rasterio.shutil module

Raster file management.

`rasterio.shutil.copy(src, dst, driver=None, strict=True, **creation_options)`

Copy a raster from a path or open dataset handle to a new destination with driver specific creation options.

Parameters

- **src** (`str` or `PathLike` or `dataset object opened in 'r' mode`) – Source dataset
- **dst** (`str` or `PathLike`) – Output dataset path
- **driver** (`str`, *optional*) – Output driver name
- **strict** (`bool`, *optional*. Default: `True`) – Indicates if the output must be strictly equivalent or if the driver may adapt as necessary
- **creation_options** (`dict`, *optional*) – Creation options for output dataset

Return type`None``rasterio.shutil.copyfiles(src, dst)`

Copy files associated with a dataset from one location to another.

Parameters

- **src** (`str` or `PathLike`) – Source dataset
- **dst** (`str` or `PathLike`) – Target dataset

Return type`None``rasterio.shutil.delete(path, driver=None)`

Delete a GDAL dataset

Parameters

- **path** (`path`) – Path to dataset to delete
- **driver** (`str` or `None`, *optional*) – Name of driver to use for deleting. Defaults to whatever GDAL determines is the appropriate driver

`rasterio.shutil.exists(path)`

Determine if a dataset exists by attempting to open it.

Parameters`path` (`str`) – Path to dataset

rasterio.tools module

Rasterio tools module

See this RFC about Rasterio tools: <https://github.com/rasterio/rasterio/issues/1300>.

class rasterio.tools.JSONSequenceTool(func)

Bases: `object`

Extracts data from a dataset file and saves a JSON sequence

rasterio.transform module

Geospatial transforms

class rasterio.transform.AffineTransformer(affine_transform)

Bases: `TransformerBase`

A pure Python class related to affine based coordinate transformations.

class rasterio.transform.GCPTransformer(gcps)

Bases: `GCPTransformerBase, GDALTransformerBase`

Class related to Ground Control Point (GCPs) based coordinate transformations.

Uses `GDALCreateGCPTransformer` and `GDALGCPTransform` for computations. Ensure that GDAL transformer objects are destroyed by calling `close()` method or using context manager interface.

class rasterio.transform.GDALTransformerBase

Bases: `TransformerBase`

close()

class rasterio.transform.RPCTransformer(rpcs, **rpc_options)

Bases: `RPCTransformerBase, GDALTransformerBase`

Class related to Rational Polynomial Coefficients (RPCs) based coordinate transformations.

Uses `GDALCreateRPCTransformer` and `GDALRPCTransform` for computations. Options for `GDALCreateRPCTransformer` may be passed using `rpc_options`. Ensure that GDAL transformer objects are destroyed by calling `close()` method or using context manager interface.

class rasterio.transform.TransformMethodsMixin

Bases: `object`

Mixin providing methods for calculations related to transforming between rows and columns of the raster array and the coordinates.

These methods are wrappers for the functionality in `rasterio.transform` module.

A subclass with this mixin MUST provide a `transform` property.

index(x, y, z=None, op=<built-in function floor>, precision=None, transform_method=TransformMethod.affine, **rpc_options)

Get the (row, col) index of the pixel containing (x, y).

Parameters

- **x** (`float`) – x value in coordinate reference system
- **y** (`float`) – y value in coordinate reference system

- **z** (*float, optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **op** (*function, optional (default: math.floor)*) – Function to convert fractional pixels to whole numbers (floor, ceiling, round)
- **transform_method** (*TransformMethod, optional*) – The coordinate transformation method. Default: *TransformMethod.affine*.
- **rpc_options** (*dict, optional*) – Additional arguments passed to GDALCreateRPC-Transformer
- **precision** (*int, optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns

(row index, col index)

Return type

tuple

xy(row, col, z=None, offset='center', transform_method=TransformMethod.affine, **rpc_options)

Get the coordinates x, y of a pixel at row, col.

The pixel's center is returned by default, but a corner can be returned by setting *offset* to one of *ul*, *ur*, *ll*, *lr*.**Parameters**

- **row** (*int*) – Pixel row.
- **col** (*int*) – Pixel column.
- **z** (*float, optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **offset** (*str, optional*) – Determines if the returned coordinates are for the center of the pixel or for a corner.
- **transform_method** (*TransformMethod, optional*) – The coordinate transformation method. Default: *TransformMethod.affine*.
- **rpc_options** (*dict, optional*) – Additional arguments passed to GDALCreateRPC-Transformer

Returns

x, y

Return type

tuple

class rasterio.transform.TransformerBaseBases: *object*

Generic GDAL transformer base class

Notes

Subclasses must have a `_transformer` attribute and implement a `_transform` method.

rowcol(xs, ys, zs=None, op=<built-in function floor>, precision=None)

Get rows and cols coordinates given geographic coordinates.

Parameters

- **xs** (`float or list of float`) – Geographic coordinates
- **ys** (`float or list of float`) – Geographic coordinates
- **zs** (`float or list of float, optional`) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **op** (`function, optional (default: math.floor)`) – Function to convert fractional pixels to whole numbers (floor, ceiling, round)
- **precision** (`int, optional (default: None)`) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Raises

`ValueError` – If input coordinates are not all equal length

Return type

`tuple of float or list of float`.

xy(rows, cols, zs=None, offset='center')

Returns geographic coordinates given dataset rows and cols coordinates

Parameters

- **rows** (`int or list of int`) – Image pixel coordinates
- **cols** (`int or list of int`) – Image pixel coordinates
- **zs** (`float or list of float, optional`) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **offset** (`str, optional`) – Determines if the returned coordinates are for the center of the pixel or for a corner.

Raises

`ValueError` – If input coordinates are not all equal length

Return type

`tuple of float or list of float`

rasterio.transform.array_bounds(height, width, transform)

Return the bounds of an array given height, width, and a transform.

Return the `west, south, east, north` bounds of an array given its height, width, and an affine transform.

rasterio.transform.from_bounds(west, south, east, north, width, height)

Return an Affine transformation given bounds, width and height.

Return an Affine transformation for a georeferenced raster given its bounds `west, south, east, north` and its `width` and `height` in number of pixels.

rasterio.transform.from_gcps(*gcps*)

Make an Affine transform from ground control points.

Parameters

gcps (*sequence of GroundControlPoint*) – Such as the first item of a dataset’s *gcps* property.

Return type

Affine

rasterio.transform.from_origin(*west*, *north*, *xsize*, *ysize*)

Return an Affine transformation given upper left and pixel sizes.

Return an Affine transformation for a georeferenced raster given the coordinates of its upper left corner *west*, *north* and pixel sizes *xsize*, *ysize*.

rasterio.transform.get_transformer(*transform*, *rpc_options*)**

Return the appropriate transformer class

rasterio.transform.guard_transform(*transform*)

Return an Affine transformation instance.

rasterio.transform.rowcol(*transform*, *xs*, *ys*, *zs=None*, *op=<built-in function floor>*, *precision=None*, *rpc_options*)**

Get rows and cols of the pixels containing (x, y).

Parameters

- **transform** (*Affine or sequence of GroundControlPoint or RPC*) – Transform suitable for input to `AffineTransform`, `GCPTransformer`, or `RPCTransformer`.
- **xs** (*list or float*) – x values in coordinate reference system.
- **ys** (*list or float*) – y values in coordinate reference system.
- **zs** (*list or float, optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **op** (*function*) – Function to convert fractional pixels to whole numbers (floor, ceiling, round).
- **precision** (*int or float, optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.
- **rpc_options** (*dict, optional*) – Additional arguments passed to `GDALCreateRPCTransformer`.

Returns

- **rows** (*list of ints*) – list of row indices
- **cols** (*list of ints*) – list of column indices

rasterio.transform.tastes_like_gdal(*seq*)

Return True if *seq* matches the GDAL geotransform pattern.

rasterio.transform.xy(*transform*, *rows*, *cols*, *zs=None*, *offset='center'*, *rpc_options*)**

Get the x and y coordinates of pixels at *rows* and *cols*.

The pixel’s center is returned by default, but a corner can be returned by setting *offset* to one of *ul*, *ur*, *ll*, *lr*.

Supports affine, Ground Control Point (GCP), or Rational Polynomial Coefficients (RPC) based coordinate transformations.

Parameters

- **transform** (*Affine or sequence of GroundControlPoint or RPC*) – Transform suitable for input to `AffineTransform`, `GCPTransformer`, or `RPCTransformer`.
- **rows** (*list or int*) – Pixel rows.
- **cols** (*int or sequence of ints*) – Pixel columns.
- **zs** (*list or float, optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **offset** (*str, optional*) – Determines if the returned coordinates are for the center of the pixel or for a corner.
- **rpc_options** (*dict, optional*) – Additional arguments passed to `GDALCreateRPCTransformer`.

Returns

- **xs** (*float or list of floats*) – x coordinates in coordinate reference system
- **ys** (*float or list of floats*) – y coordinates in coordinate reference system

rasterio.vrt module

`rasterio.vrt`: a module concerned with GDAL VRTs

class rasterio.vrt.WarpedVRT

Bases: `WarpedVRTReaderBase`, `WindowMethodsMixin`, `TransformMethodsMixin`

A virtual warped dataset.

Abstracts the details of raster warping and allows access to data that is reprojected when read.

This class is backed by an in-memory GDAL `VRTWarpedDataset` VRT file.

Parameters

- **src_dataset** (*dataset object*) – The warp source.
- **src_crs** (*CRS or str, optional*) – Overrides the coordinate reference system of `src_dataset`.
- **src_transform** (*Affine, optional*) – Overrides the transform of `src_dataset`.
- **src_nodata** (*float, optional*) – Overrides the nodata value of `src_dataset`, which is the default.
- **crs** (*CRS or str, optional*) – The coordinate reference system at the end of the warp operation. Default: the crs of `src_dataset`. `dst_crs` was a deprecated alias for this parameter.
- **transform** (*Affine, optional*) – The transform for the virtual dataset. Default: will be computed from the attributes of `src_dataset`. `dst_transform` was a deprecated alias for this parameter.
- **height** (*int, optional*) – The dimensions of the virtual dataset. Defaults: will be computed from the attributes of `src_dataset`. `dst_height` and `dst_width` were deprecated alias for these parameters.
- **width** (*int, optional*) – The dimensions of the virtual dataset. Defaults: will be computed from the attributes of `src_dataset`. `dst_height` and `dst_width` were deprecated alias for these parameters.

- **nodata** (`float`, *optional*) – Nodata value for the virtual dataset. Default: the nodata value of `src_dataset` or 0.0. `dst_nodata` was a deprecated alias for this parameter.
- **resampling** (`Resampling`, *optional*) – Warp resampling algorithm. Default: `Resampling.nearest`.
- **tolerance** (`float`, *optional*) – The maximum error tolerance in input pixels when approximating the warp transformation. Default: 0.125, or one-eighth of a pixel.
- **src_alpha** (`int`, *optional*) – Index of a source band to use as an alpha band for warping.
- **dst_alpha** (`int`, *optional*) – Index of a destination band to use as an alpha band for warping.
- **add_alpha** (`bool`, *optional*) – Whether to add an alpha masking band to the virtual dataset. Default: False. This option will cause deletion of the VRT nodata value.
- **init_dest_nodata** (`bool`, *optional*) – Whether or not to initialize output to `nodata`. Default: True.
- **warp_mem_limit** (`int`, *optional*) – The warp operation's memory limit in MB. The default (0) means 64 MB with GDAL 2.2.
- **dtype** (`str`, *optional*) – The working data type for warp operation and output.
- **warp_extras** (`dict`) – GDAL extra warp options. See <https://gdal.org/doxygen/structGDALWarpOptions.html>.

src_dataset

The dataset object to be virtually warped.

Type

`dataset`

resampling

One of the values from `rasterio.enums.Resampling`. The default is `Resampling.nearest`.

Type

`int`

tolerance

The maximum error tolerance in input pixels when approximating the warp transformation. The default is 0.125.

Type

`float`

src_nodata

The source nodata value. Pixels with this value will not be used for interpolation. If not set, it will be default to the nodata value of the source image, if available.

Type

`int` or `float`, optional

dst_nodata

The nodata value used to initialize the destination; it will remain in all areas not covered by the reprojected source. Defaults to the value of `src_nodata`, or 0 (gdal default).

Type

`int` or `float`, optional

working_dtype

The working data type for warp operation and output.

Type

`str`, optional

warp_extras

GDAL extra warp options. See <https://gdal.org/doxygen/structGDALWarpOptions.html>.

Type

`dict`

Examples

```
>>> with rasterio.open('tests/data/RGB.byte.tif') as src:
...     with WarpedVRT(src, crs='EPSG:3857') as vrt:
...         data = vrt.read()
```

block_shapes

An ordered list of block shapes for each bands

Shapes are tuples and have the same ordering as the dataset's shape: (count of image rows, count of image columns).

Return type

`list`

block_size(bidx, i, j)

Returns the size in bytes of a particular block

Only useful for TIFF formatted datasets.

Parameters

- **bidx** (`int`) – Band index, starting with 1.
- **i** (`int`) – Row index of the block, starting with 0.
- **j** (`int`) – Column index of the block, starting with 0.

Return type

`int`

block_window(bidx, i, j)

Returns the window for a particular block

Parameters

- **bidx** (`int`) – Band index, starting with 1.
- **i** (`int`) – Row index of the block, starting with 0.
- **j** (`int`) – Column index of the block, starting with 0.

Return type

`Window`

block_windows(bidx=0)

Iterator over a band's blocks and their windows

The primary use of this method is to obtain windows to pass to `read()` for highly efficient access to raster block data.


The positional parameter `bidx` takes the index (starting at 1) of the desired band. This iterator yields blocks “left to right” and “top to bottom” and is similar to Python’s `enumerate()` in that the first element is the block index and the second is the dataset window.

Blocks are built-in to a dataset and describe how pixels are grouped within each band and provide a mechanism for efficient I/O. A window is a range of pixels within a single band defined by row start, row stop, column start, and column stop. For example, `((0, 2), (0, 2))` defines a 2 x 2 window at the upper left corner of a raster band. Blocks are referenced by an `(i, j)` tuple where `(0, 0)` would be a band’s upper left block.

Raster I/O is performed at the block level, so accessing a window spanning multiple rows in a striped raster requires reading each row. Accessing a 2 x 2 window at the center of a 1800 x 3600 image requires reading 2 rows, or 7200 pixels just to get the target 4. The same image with internal 256 x 256 blocks would require reading at least 1 block (if the window entire window falls within a single block) and at most 4 blocks, or at least 512 pixels and at most 2048.

Given an image that is 512 x 512 with blocks that are 256 x 256, its blocks and windows would look like:

Blocks:



Windows:

```

UL: ((0, 256), (0, 256))
UR: ((0, 256), (256, 512))
LL: ((256, 512), (0, 256))
LR: ((256, 512), (256, 512))

```

Parameters

`bidx (int, optional)` – The band index (using 1-based indexing) from which to extract windows. A value less than 1 uses the first band if all bands have homogeneous windows and raises an exception otherwise.

Yields

`block, window`

bounds

Returns the lower left and upper right bounds of the dataset in the units of its coordinate reference system.

The returned value is a tuple: (lower left x, lower left y, upper right x, upper right y)

checksum(`bidx, window=None`)

Compute an integer checksum for the stored band

Parameters

- **band** (`int`) – The band’s index (1-indexed).
- **window** (`tuple`, *optional*) – A window of the band. Default is the entire extent of the band.

Return type

An int.

close()

Close the dataset and unwind attached exit stack.

closed

Test if the dataset is closed

Return type`bool`**colorinterp**A sequence of `ColorInterp.<enum>` in band order.**Return type**`tuple`**colormap(bidx)**

Returns a dict containing the colormap for a band.

Parameters

- **bidx** (`int`) – Index of the band whose colormap will be returned. Band index starts at 1.

Returns

Mapping of color index value (starting at 0) to RGBA color as a 4-element tuple.

Return type`dict`**Raises**

- **ValueError** – If no colormap is found for the specified band (NULL color table).
- **IndexError** – If no band exists for the provided index.

compression**count**

The number of raster bands in the dataset

Return type`int`**crs**

The dataset’s coordinate reference system

dataset_mask(*out=None*, *out_shape=None*, *window=None*, *boundless=False*,
resampling=Resampling.nearest)

Get the dataset’s 2D valid data mask.

Parameters

- **out** (`numpy ndarray`, *optional*) – As with Numpy ufuncs, this is an optional reference to an output array with the same dimensions and shape into which data will be placed.

Note: the method’s return value may be a view on this array. In other words, *out* is likely to be an incomplete representation of the method’s results.

Cannot be combined with *out_shape*.

- **out_shape** (*tuple*, *optional*) – A tuple describing the output array’s shape. Allows for decimated reads without constructing an output Numpy array.

Cannot be combined with *out*.

- **window** (*a pair (tuple) of pairs of ints or Window, optional*) – The optional *window* argument is a 2 item tuple. The first item is a tuple containing the indexes of the rows at which the window starts and stops and the second is a tuple containing the indexes of the columns at which the window starts and stops. For example, ((0, 2), (0, 2)) defines a 2x2 window at the upper left of the raster dataset.
- **boundless** (*bool, optional (default False)*) – If *True*, windows that extend beyond the dataset’s extent are permitted and partially or completely filled arrays will be returned as appropriate.
- **resampling** (*Resampling*) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.

Returns

The dtype of this array is uint8. 0 = nodata, 255 = valid data.

Return type

Numpy ndarray or a view on a Numpy ndarray

Notes

Note: as with Numpy ufuncs, an object is returned even if you use the optional *out* argument and the return value shall be preferentially used by callers.

The dataset mask is calculated based on the individual band masks according to the following logic, in order of precedence:

1. If a .msk file, dataset-wide alpha, or internal mask exists it will be used for the dataset mask.
2. Else if the dataset is a 4-band with a shadow nodata value, band 4 will be used as the dataset mask.
3. If a nodata value exists, use the binary OR (|) of the band masks 4. If no nodata value exists, return a mask filled with 255.

Note that this differs from `read_masks` and GDAL RFC15 in that it applies per-dataset, not per-band (see https://trac.osgeo.org/gdal/wiki/rfc15_nodatabitmask)

descriptions

Descriptions for each dataset band

To set descriptions, one for each band is required.

Return type

list of str

driver

dtypes

The data types of each band in index order

Return type

list of str

files

Returns a sequence of files associated with the dataset.

Return type

tuple

gcps

ground control points and their coordinate reference system.

This property is a 2-tuple, or pair: (gcps, crs).

gcps

[list of GroundControlPoint] Zero or more ground control points.

crs: CRS

The coordinate reference system of the ground control points.

get_gcps()

Get GCPs and their associated CRS.

get_nodatavals()**get_tag_item(ns, dm=None, bidx=0, ovr=None)**

Returns tag item value

Parameters

- **ns** (*str*) – The key for the metadata item to fetch.
- **dm** (*str*) – The domain to fetch for.
- **bidx** (*int*) – Band index, starting with 1.
- **ovr** (*int*) – Overview level

Return type

str

get_transform()

Returns a GDAL geotransform in its native form.

height**index(x, y, z=None, op=<built-in function floor>, precision=None, transform_method=TransformMethod.affine, **rpc_options)**

Get the (row, col) index of the pixel containing (x, y).

Parameters

- **x** (*float*) – x value in coordinate reference system
- **y** (*float*) – y value in coordinate reference system
- **z** (*float, optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **op** (*function, optional (default: math.floor)*) – Function to convert fractional pixels to whole numbers (floor, ceiling, round)
- **transform_method** (*TransformMethod, optional*) – The coordinate transformation method. Default: *TransformMethod.affine*.
- **rpc_options** (*dict, optional*) – Additional arguments passed to GDALCreateRPC-Transformer

- **precision** (`int`, *optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns

(row index, col index)

Return type`tuple`**indexes**

The 1-based indexes of each band in the dataset

For a 3-band dataset, this property will be [1, 2, 3].

Return type`list of int`**interleaving****is_tiled****lnglat()****mask_flagEnums**

Sets of flags describing the sources of band masks.

Parameters

- **all_valid** (*There are no invalid pixels, all mask values will be*) – 255. When used this will normally be the only flag set.
- **per_dataset** (*The mask band is shared between all bands on the*) – dataset.
- **alpha** (*The mask band is actually an alpha band and may have*) – values other than 0 and 255.
- **nodata** (*Indicates the mask is actually being generated from*) – nodata values (mutually exclusive of “alpha”).

ReturnsOne list of `rasterio.enums.MaskFlags` members per band.**Return type**`list [, list*]`**Examples**

For a 3 band dataset that has masks derived from nodata values:

```
>>> dataset.mask_flagEnums
([<MaskFlags.nodata: 8>], [<MaskFlags.nodata: 8>], [<MaskFlags.nodata: 8>])
>>> band1_flags = dataset.mask_flagEnums[0]
>>> rasterio.enums.MaskFlags.nodata in band1_flags
True
>>> rasterio.enums.MaskFlags.alpha in band1_flags
False
```

meta

The basic metadata of this dataset.

mode**name****nodata**

The dataset's single nodata value

Notes

May be set.

Return type

float

nodatavals

Nodata values for each band

Notes

This may not be set.

Return type

list of float

offsets

Raster offset for each dataset band

To set offsets, one for each band is required.

Return type

list of float

options**overviews(*bidx*)****photometric****profile**

Basic metadata and creation options of this dataset.

May be passed as keyword arguments to `rasterio.open()` to create a clone of this dataset.

read(*indexes=None, out=None, window=None, masked=False, out_shape=None, resampling=Resampling.nearest, fill_value=None, out_dtype=None, **kwargs*)

Read a dataset's raw pixels as an N-d array

This data is read from the dataset's band cache, which means that repeated reads of the same windows may avoid I/O.

Parameters

- **indexes** (*list of ints or a single int, optional*) – If *indexes* is a list, the result is a 3D array, but is a 2D array if it is a band index number.
- **out** (*numpy ndarray, optional*) – As with Numpy ufuncs, this is an optional reference to an output array into which data will be placed. If the height and width of *out* differ from that of the specified window (see below), the raster image will be decimated or replicated using the specified resampling method (also see below).

Note: the method’s return value may be a view on this array. In other words, *out* is likely to be an incomplete representation of the method’s results.

This parameter cannot be combined with *out_shape*.

- **out_dtype** (*str* or *numpy dtype*) – The desired output data type. For example: ‘uint8’ or rasterio.uint16.
- **out_shape** (*tuple*, *optional*) – A tuple describing the shape of a new output array. See *out* (above) for notes on image decimation and replication.
Cannot combined with *out*.
- **window** (*a pair (tuple) of pairs of ints or Window, optional*) – The optional *window* argument is a 2 item tuple. The first item is a tuple containing the indexes of the rows at which the window starts and stops and the second is a tuple containing the indexes of the columns at which the window starts and stops. For example, ((0, 2), (0, 2)) defines a 2x2 window at the upper left of the raster dataset.
- **masked** (*bool*, *optional*) – If *masked* is *True* the return value will be a masked array. Otherwise (the default) the return value will be a regular array. Masks will be exactly the inverse of the GDAL RFC 15 conforming arrays returned by *read_masks()*.
- **resampling** (*Resampling*) – By default, pixel values are read raw or interpolated using a nearest neighbor algorithm from the band cache. Other resampling algorithms may be specified. Resampled pixels are not cached.
- **fill_value** (*scalar*) – Fill value applied in the *boundless=True* case only.
- **kwargs** (*dict*) – This is only for backwards compatibility. No keyword arguments are supported other than the ones named above.

Returns

- *Numpy ndarray or a view on a Numpy ndarray*
- **Note** (as with Numpy ufuncs, an object is returned even if you)
use the optional *out* argument and the return value shall be
preferentially used by callers.

read_crs()

Return the GDAL dataset’s stored CRS

read_masks(indexes=None, out=None, out_shape=None, window=None, resampling=Resampling.nearest, **kwargs)

Read raster band masks as a multidimensional array

read_transform()

Return the stored GDAL GeoTransform

res

Returns the (width, height) of pixels in the units of its coordinate reference system.

rpcs

Rational polynomial coefficients mapping between pixel and geodetic coordinates.

This property is a dict-like object.

rpcs : RPC instance containing coefficients. Empty if dataset does not have any metadata in the “RPC” domain.

sample(*xy, indexes=None, masked=False*)

Get the values of a dataset at certain positions

Values are from the nearest pixel. They are not interpolated.

Parameters

- **xy** (*iterable*) – Pairs of x, y coordinates (floats) in the dataset’s reference system.
- **indexes** (*int or list of int*) – Indexes of dataset bands to sample.
- **masked** (*bool*, *default: False*) – Whether to mask samples that fall outside the extent of the dataset.

Returns

Arrays of length equal to the number of specified indexes containing the dataset values for the bands corresponding to those indexes.

Return type

iterable

scales

Raster scale for each dataset band

To set scales, one for each band is required.

Return type

list of float

shape**start()**

Start the dataset’s life cycle

statistics(*bidx, approx=False, clear_cache=False*)

Get min, max, mean, and standard deviation of a raster band.

Parameters

- **bidx** (*int*) – The band’s index (1-indexed).
- **approx** (*bool, optional*) – If True, statistics will be calculated from reduced resolution data.
- **clear_cache** (*bool, optional*) – If True, saved stats will be deleted and statistics will be recomputed. Requires GDAL version >= 3.2.

Return type

Statistics

Notes

GDAL will preferentially use statistics kept in raster metadata like images tags or an XML sidecar. If that metadata is out of date, the statistics may not correspond to the actual data.

Additionally, GDAL will save statistics to file metadata as a side effect if that metadata does not already exist.

stop()

Close the GDAL dataset handle

subdatasets

Sequence of subdatasets

tag_namespaces(bidx=0)

Get a list of the dataset's metadata domains.

Returned items may be passed as *ns* to the tags method.

Parameters

- **int (bidx)** – Can be used to select a specific band, otherwise the dataset's general metadata domains are returned.
- **optional** – Can be used to select a specific band, otherwise the dataset's general metadata domains are returned.

Return type

list of str

tags(bidx=0, ns=None)

Returns a dict containing copies of the dataset or band's tags.

Tags are pairs of key and value strings. Tags belong to namespaces. The standard namespaces are: default (None) and 'IMAGE_STRUCTURE'. Applications can create their own additional namespaces.

The optional bidx argument can be used to select the tags of a specific band. The optional ns argument can be used to select a namespace other than the default.

transform

The dataset's georeferencing transformation matrix

This transform maps pixel row/column coordinates to coordinates in the dataset's coordinate reference system.

Return type

Affine

units

one units string for each dataset band

Possible values include 'meters' or 'degC'. See the Pint project for a suggested list of units.

To set units, one for each band is required.

Return type

list of str

Type

A list of str

width

window(left, bottom, right, top, precision=None)

Get the window corresponding to the bounding coordinates.

The resulting window is not cropped to the row and column limits of the dataset.

Parameters

- **left** (*float*) – Left (west) bounding coordinate
- **bottom** (*float*) – Bottom (south) bounding coordinate
- **right** (*float*) – Right (east) bounding coordinate

- **top** (*float*) – Top (north) bounding coordinate
- **precision** (*int*, *optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns
`window`

Return type
`Window`

window_bounds(*window*)

Get the bounds of a window

Parameters
`window` (`rasterio.windows.Window`) – Dataset window

Returns
`bounds` – x_min, y_min, x_max, y_max for the given window

Return type
`tuple`

window_transform(*window*)

Get the affine transform for a dataset window.

Parameters
`window` (`rasterio.windows.Window`) – Dataset window

Returns
`transform` – The affine transform matrix for the given window

Return type
Affine

write_transform(*value*)

xy(*row*, *col*, *z=None*, *offset='center'*, *transform_method=TransformMethod.affine*, ***rpc_options*)

Get the coordinates x, y of a pixel at row, col.

The pixel's center is returned by default, but a corner can be returned by setting *offset* to one of *ul*, *ur*, *ll*, *lr*.

Parameters

- **row** (*int*) – Pixel row.
- **col** (*int*) – Pixel column.
- **z** (*float*, *optional*) – Height associated with coordinates. Primarily used for RPC based coordinate transformations. Ignored for affine based transformations. Default: 0.
- **offset** (*str*, *optional*) – Determines if the returned coordinates are for the center of the pixel or for a corner.
- **transform_method** (`TransformMethod`, *optional*) – The coordinate transformation method. Default: `TransformMethod.affine`.
- **rpc_options** (*dict*, *optional*) – Additional arguments passed to GDALCreateRPC-Transformer

Returns
`x, y`

Return type
`tuple`

rasterio.warp module

Raster warping and reprojection.

`rasterio.warp.aligned_target(transform, width, height, resolution)`

Aligns target to specified resolution

Parameters

- **transform** (`Affine`) – Input affine transformation matrix
- **width** (`int`) – Input dimensions
- **height** (`int`) – Input dimensions
- **resolution** (`tuple (x_resolution, y_resolution) or float`) – Target resolution, in units of target coordinate reference system.

Returns

- **transform** (`Affine`) – Output affine transformation matrix
- **width, height** (`int`) – Output dimensions

`rasterio.warp.calculate_default_transform(src_crs, dst_crs, width, height, left=None, bottom=None, right=None, top=None, gcps=None, rpcs=None, resolution=None, dst_width=None, dst_height=None, **kwargs)`

Output dimensions and transform for a reprojection.

Source and destination coordinate reference systems and output width and height are the first four, required, parameters. Source georeferencing can be specified using either ground control points (gcps) or spatial bounds (left, bottom, right, top). These two forms of georeferencing are mutually exclusive.

The destination transform is anchored at the left, top coordinate.

Destination width and height (and resolution if not provided), are calculated using GDAL's method for suggest warp output.

Parameters

- **src_crs** (`CRS or dict`) – Source coordinate reference system, in rasterio dict format. Example: `CRS({'init': 'EPSG:4326'})`
- **dst_crs** (`CRS or dict`) – Target coordinate reference system.
- **width** (`int`) – Source raster width and height.
- **height** (`int`) – Source raster width and height.
- **left** (`float, optional`) – Bounding coordinates in src_crs, from the bounds property of a raster. Required unless using gcps.
- **bottom** (`float, optional`) – Bounding coordinates in src_crs, from the bounds property of a raster. Required unless using gcps.
- **right** (`float, optional`) – Bounding coordinates in src_crs, from the bounds property of a raster. Required unless using gcps.
- **top** (`float, optional`) – Bounding coordinates in src_crs, from the bounds property of a raster. Required unless using gcps.
- **gcps** (`sequence of GroundControlPoint, optional`) – Instead of a bounding box for the source, a sequence of ground control points may be provided.

- **rpcls** (*RPC or dict, optional*) – Instead of a bounding box for the source, rational polynomial coefficients may be provided.
- **resolution** (*tuple (x resolution, y resolution) or float, optional*) – Target resolution, in units of target coordinate reference system.
- **dst_width** (*int, optional*) – Output file size in pixels and lines. Cannot be used together with resolution.
- **dst_height** (*int, optional*) – Output file size in pixels and lines. Cannot be used together with resolution.
- **kwags** (*dict, optional*) – Additional arguments passed to transformation function.

Returns

- **transform** (*Affine*) – Output affine transformation matrix
- **width, height** (*int*) – Output dimensions

Notes

Some behavior of this function is determined by the CHECK_WITH_INVERT_PROJ environment variable:

YES

constrain output raster to extents that can be inverted avoids visual artifacts and coordinate discontinuities.

NO

reproject coordinates beyond valid bound limits

```
rasterio.warp.reproject(source, destination=None, src_transform=None, gcps=None,
                        src_crs=None, src_nodata=None, dst_transform=None, dst_crs=None,
                        dst_nodata=None, dst_resolution=None, src_alpha=0, dst_alpha=0,
                        resampling=Resampling.nearest, num_threads=1, init_dest_nodata=True,
                        warp_mem_limit=0, **kwags)
```

Reproject a source raster to a destination raster.

If the source and destination are ndarrays, coordinate reference system definitions and affine transformation parameters or ground control points (gcps) are required for reprojection.

If the source and destination are rasterio Bands, shorthand for bands of datasets on disk, the coordinate reference systems and transforms or GCPs will be read from the appropriate datasets.

Parameters

- **source** (*ndarray or Band*) – The source is a 2 or 3-D ndarray, or a single or a multiple Rasterio Band object. The dimensionality of source and destination must match, i.e., for multiband reprojection the lengths of the first axes of the source and destination must be the same.
- **destination** (*ndarray or Band, optional*) – The destination is a 2 or 3-D ndarray, or a single or a multiple Rasterio Band object. The dimensionality of source and destination must match, i.e., for multiband reprojection the lengths of the first axes of the source and destination must be the same.
- **src_transform** (*affine.Affine(), optional*) – Source affine transformation. Required if source and destination are ndarrays. Will be derived from source if it is a rasterio Band. An error will be raised if this parameter is defined together with gcps.

- **gcps** (*sequence of GroundControlPoint, optional*) – Ground control points for the source. An error will be raised if this parameter is defined together with src_transform or rpcs.
- **rpcs** (*RPC or dict, optional*) – Rational polynomial coefficients for the source. An error will be raised if this parameter is defined together with src_transform or gcps.
- **src_crs** (*CRS or dict, optional*) – Source coordinate reference system, in rasterio dict format. Required if source and destination are ndarrays. Will be derived from source if it is a rasterio Band. Example: CRS({‘init’: ‘EPSG:4326’})
- **src_nodata** (*int or float, optional*) – The source nodata value. Pixels with this value will not be used for interpolation. If not set, it will default to the nodata value of the source image if a masked ndarray or rasterio band, if available.
- **dst_transform** (*affine.Affine(), optional*) – Target affine transformation. Required if source and destination are ndarrays. Will be derived from target if it is a rasterio Band.
- **dst_crs** (*CRS or dict, optional*) – Target coordinate reference system. Required if source and destination are ndarrays. Will be derived from target if it is a rasterio Band.
- **dst_nodata** (*int or float, optional*) – The nodata value used to initialize the destination; it will remain in all areas not covered by the reprojected source. Defaults to the nodata value of the destination image (if set), the value of src_nodata, or 0 (GDAL default).
- **dst_resolution** (*tuple (x resolution, y resolution) or float, optional*) – Target resolution, in units of target coordinate reference system.
- **src_alpha** (*int, optional*) – Index of a band to use as the alpha band when warping.
- **dst_alpha** (*int, optional*) – Index of a band to use as the alpha band when warping.
- **resampling** (*int, rasterio.enums.Resampling*) – Resampling method to use. Default is *rasterio.enums.Resampling.nearest*. An exception will be raised for a method not supported by the running version of GDAL.
- **num_threads** (*int, optional*) – The number of warp worker threads. Default: 1.
- **init_dest_nodata** (*bool*) – Flag to specify initialization of nodata in destination; prevents overwrite of previous warps. Defaults to True.
- **warp_mem_limit** (*int, optional*) – The warp operation memory limit in MB. Larger values allow the warp operation to be carried out in fewer chunks. The amount of memory required to warp a 3-band uint8 2000 row x 2000 col raster to a destination of the same size is approximately 56 MB. The default (0) means 64 MB with GDAL 2.2.
- **kwargs** (*dict, optional*) – Additional arguments passed to both the image to image transformer *GDALCreateGenImgProjTransformer2()* (for example, MAX_GCP_ORDER=2) and the *GDALWarpOptions* (for example, INIT_DEST=NO_DATA).

Returns

- **destination** (*ndarray or Band*) – The transformed ndarray or Band.
- **dst_transform** (*Affine*) – The affine transformation matrix of the destination.

`rasterio.warp.transform(src_crs, dst_crs, xs, ys, zs=None)`

Transform vectors from source to target coordinate reference system.

Transform vectors of x, y and optionally z from source coordinate reference system into target.

Parameters

- **src_crs** (`CRS or dict`) – Source coordinate reference system, as a rasterio CRS object. Example: `CRS({'init': 'EPSG:4326'})`
- **dst_crs** (`CRS or dict`) – Target coordinate reference system.
- **xs (array_like)** – Contains x values. Will be cast to double floating point values.
- **ys (array_like)** – Contains y values.
- **zs (array_like, optional)** – Contains z values. Assumed to be all 0 if absent.

Returns

out – Tuple of x, y, and optionally z vectors, transformed into the target coordinate reference system.

Return type

`tuple` of array_like, (xs, ys, [zs])

`rasterio.warp.transform_bounds(src_crs, dst_crs, left, bottom, right, top, densify_pts=21)`

Transform bounds from src_crs to dst_crs.

Optionally densifying the edges (to account for nonlinear transformations along these edges) and extracting the outermost bounds.

Note: antimeridian support added in version 1.3.0

Parameters

- **src_crs** (`CRS or dict`) – Source coordinate reference system, in rasterio dict format. Example: `CRS({'init': 'EPSG:4326'})`
- **dst_crs** (`CRS or dict`) – Target coordinate reference system.
- **left** (`float`) – Bounding coordinates in src_crs, from the bounds property of a raster.
- **bottom** (`float`) – Bounding coordinates in src_crs, from the bounds property of a raster.
- **right** (`float`) – Bounding coordinates in src_crs, from the bounds property of a raster.
- **top** (`float`) – Bounding coordinates in src_crs, from the bounds property of a raster.
- **densify_pts** (`uint, optional`) – Number of points to add to each edge to account for nonlinear edges produced by the transform process. Large numbers will produce worse performance. Default: 21 (gdal default).

Returns

left, bottom, right, top – Outermost coordinates in target coordinate reference system.

Return type

`float`

`rasterio.warp.transform_geom(src_crs, dst_crs, geom, antimeridian_cutting=True, antimeridian_offset=10.0, precision=-1)`

Transform geometry from source coordinate reference system into target.

Parameters

- **src_crs** (`CRS or dict`) – Source coordinate reference system, in rasterio dict format. Example: `CRS({'init': 'EPSG:4326'})`
- **dst_crs** (`CRS or dict`) – Target coordinate reference system.
- **geom** (`GeoJSON like dict object or iterable of GeoJSON like objects.`) –

- **antimeridian_cutting** (`bool`, *optional*) – If True, cut geometries at the antimeridian, otherwise geometries will not be cut (default). If False and GDAL is 2.2.0 or newer an exception is raised. Antimeridian cutting is always on as of GDAL 2.2.0 but this could produce an unexpected geometry.
- **antimeridian_offset** (`float`) – Offset from the antimeridian in degrees (default: 10) within which any geometries will be split.
- **precision** (`float`) – If ≥ 0 , geometry coordinates will be rounded to this number of decimal places after the transform operation, otherwise original coordinate values will be preserved (default).

Returns

out – Transformed geometry(s) in GeoJSON dict format

Return type

GeoJSON like dict object or `list` of GeoJSON like objects.

rasterio.windows module

Window utilities and related functions.

A window is an instance of Window

`Window(column_offset, row_offset, width, height)`

or a 2D N-D array indexer in the form of a tuple.

`((row_start, row_stop), (col_start, col_stop))`

The latter can be evaluated within the context of a given height and width and a boolean flag specifying whether the evaluation is boundless or not. If `boundless=True`, negative index values do not mean index from the end of the array dimension as they do in the `boundless=False` case.

The newer float precision read-write window capabilities of Rasterio require instances of Window to be used.

class rasterio.windows.Window(`col_off`, `row_off`, `width`, `height`)

Bases: `object`

Windows are rectangular subsets of rasters.

This class abstracts the 2-tuples mentioned in the module docstring and adds methods and new constructors.

col_off, row_off

The offset for the window.

Type

`float`

width, height

Lengths of the window.

Type

`float`

Notes

Previously the lengths were called ‘num_cols’ and ‘num_rows’ but this is a bit confusing in the new float precision world and the attributes have been changed. The originals are deprecated.

`col_off`

`crop(height, width)`

Return a copy cropped to height and width

`flatten()`

A flattened form of the window.

Returns

`col_off, row_off, width, height` – Window offsets and lengths.

Return type

`float`

`classmethod from_slices(rows, cols, height=-1, width=-1, boundless=False)`

Construct a Window from row and column slices or tuples / lists of start and stop indexes. Converts the rows and cols to offsets, height, and width.

In general, indexes are defined relative to the upper left corner of the dataset: `rows=(0, 10), cols=(0, 4)` defines a window that is 4 columns wide and 10 rows high starting from the upper left.

Start indexes may be `None` and will default to 0. Stop indexes may be `None` and will default to width or height, which must be provided in this case.

Negative start indexes are evaluated relative to the lower right of the dataset: `rows=(-2, None), cols=(-2, None)` defines a window that is 2 rows high and 2 columns wide starting from the bottom right.

Parameters

- `rows` (`slice, tuple, or list`) – Slices or 2 element tuples/lists containing start, stop indexes.
- `cols` (`slice, tuple, or list`) – Slices or 2 element tuples/lists containing start, stop indexes.
- `height` (`float`) – A shape to resolve relative values against. Only used when a start or stop index is negative or a stop index is `None`.
- `width` (`float`) – A shape to resolve relative values against. Only used when a start or stop index is negative or a stop index is `None`.
- `boundless` (`bool, optional`) – Whether the inputs are bounded (default) or not.

Return type

`Window`

`height`

`intersection(other)`

Return the intersection of this window and another

Parameters

`other` (`Window`) – Another window

Return type

`Window`

round_lengths(kwds)**

Return a copy with width and height rounded.

Lengths are rounded to the nearest whole number. The offsets are not changed.

Parameters

kwds (*dict*) – Collects keyword arguments that are no longer used.

Return type

Window

round_offsets(kwds)**

Return a copy with column and row offsets rounded.

Offsets are rounded to the preceding whole number. The lengths are not changed.

Parameters

kwds (*dict*) – Collects keyword arguments that are no longer used.

Return type

Window

round_shape(kwds)****row_off****todict()**

A mapping of attribute names and values.

Return type

dict

toranges()

Makes an equivalent pair of range tuples

toslices()

Slice objects for use as an ndarray indexer.

Returns

row_slice, col_slice – A pair of slices in row, column order

Return type

slice

width**class rasterio.windows.WindowMethodsMixin**

Bases: *object*

Mixin providing methods for window-related calculations. These methods are wrappers for the functionality in *rasterio.windows* module.

A subclass with this mixin MUST provide the following properties: *transform*, *height* and *width*.

window(left, bottom, right, top, precision=None)

Get the window corresponding to the bounding coordinates.

The resulting window is not cropped to the row and column limits of the dataset.

Parameters

- **left** (*float*) – Left (west) bounding coordinate
- **bottom** (*float*) – Bottom (south) bounding coordinate

- **right** (*float*) – Right (east) bounding coordinate
- **top** (*float*) – Top (north) bounding coordinate
- **precision** (*int, optional*) – This parameter is unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns**window****Return type***Window***window_bounds**(*window*)

Get the bounds of a window

Parameters**window** (*rasterio.windows.Window*) – Dataset window**Returns****bounds** – x_min, y_min, x_max, y_max for the given window**Return type***tuple***window_transform**(*window*)

Get the affine transform for a dataset window.

Parameters**window** (*rasterio.windows.Window*) – Dataset window**Returns****transform** – The affine transform matrix for the given window**Return type***Affine***rasterio.windows.bounds**(*window, transform, height=0, width=0*)

Get the spatial bounds of a window.

Parameters

- **window** (*Window*) – The input window.
- **transform** (*Affine*) – an affine transform matrix.

Returns**left, bottom, right, top** – A tuple of spatial coordinate bounding values.**Return type***float***rasterio.windows.crop**(*window, height, width*)

Crops a window to given height and width.

Parameters

- **window** (*Window*) – The input window.
- **height** (*int*) – The number of rows and cols in the cropped window.
- **width** (*int*) – The number of rows and cols in the cropped window.

Returns

A new Window object.

Return type*Window*`rasterio.windows.evaluate(window, height, width, boundless=False)`

Evaluates a window tuple that may contain relative index values.

The height and width of the array the window targets is the context for evaluation.

Parameters

- **window** (*Window or tuple of (rows, cols)*) – The input window.
- **height** (*int*) – The number of rows or columns in the array that the window targets.
- **width** (*int*) – The number of rows or columns in the array that the window targets.

Returns

A new Window object with absolute index values.

Return type*Window*`rasterio.windows.from_bounds(left, bottom, right, top, transform=None, height=None, width=None, precision=None)`

Get the window corresponding to the bounding coordinates.

Parameters

- **left** (*float, required*) – Left (west) bounding coordinates
- **bottom** (*float, required*) – Bottom (south) bounding coordinates
- **right** (*float, required*) – Right (east) bounding coordinates
- **top** (*float, required*) – Top (north) bounding coordinates
- **transform** (*Affine, required*) – Affine transform matrix.
- **precision** (*int, optional*) – These parameters are unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.
- **height** (*int, optional*) – These parameters are unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.
- **width** (*int, optional*) – These parameters are unused, deprecated in rasterio 1.3.0, and will be removed in version 2.0.0.

Returns

A new Window.

Return type*Window***Raises**

`WindowError` – If a window can't be calculated.

`rasterio.windows.get_data_window(arr, nodata=None)`

Window covering the input array's valid data pixels.

Parameters

- **arr** (*numpy ndarray, <= 3 dimensions*) –
- **nodata** (*number*) – If None, will either return a full window if arr is not a masked array, or will use the mask to determine non-nodata pixels. If provided, it must be a number within the valid range of the dtype of the input array.

Return type*Window*`rasterio.windows.intersect(*windows)`

Test if all given windows intersect.

Parameters`windows (sequence)` – One or more Windows.**Returns**

True if all windows intersect.

Return type*bool*`rasterio.windows.intersection(*windows)`

Innermost extent of window intersections.

Will raise WindowError if windows do not intersect.

Parameters`windows (sequence)` – One or more Windows.**Return type***Window*`rasterio.windows.iter_args(function)`

Decorator to allow function to take either *args or a single iterable which gets expanded to *args.

`rasterio.windows.round_window_to_full_blocks(window, block_shapes, height=0, width=0)`

Round window to include full expanse of intersecting tiles.

Parameters

- `window (Window)` – The input window.
- `block_shapes (tuple of block shapes)` – The input raster's block shape. All bands must have the same block/stripe structure

Return type*Window*`rasterio.windows.shape(window, height=-1, width=-1)`

The shape of a window.

height and width arguments are optional if there are no negative values in the window.

Parameters

- `window (Window)` – The input window.
- `height (int, optional)` – The number of rows or columns in the array that the window targets.
- `width (int, optional)` – The number of rows or columns in the array that the window targets.

Returns

The number of rows and columns of the window.

Return type`num_rows, num_cols`

rasterio.windows.toranges(*window*)

Normalize Windows to range tuples

rasterio.windows.transform(*window, transform*)

Construct an affine transform matrix relative to a window.

Parameters

- **window** ([Window](#)) – The input window.
- **transform** ([Affine](#)) – an affine transform matrix.

Returns

The affine transform matrix for the given window

Return type

Affine

rasterio.windows.union(windows*)**

Union windows and return the outermost extent they cover.

Parameters

windows (*sequence*) – One or more Windows.

Return type

[Window](#)

rasterio.windows.validate_length_value(*instance, attribute, value*)**rasterio.windows.window_index(*window, height=0, width=0*)**

Construct a pair of slice objects for ndarray indexing

Starting indexes are rounded down, Stopping indexes are rounded up.

Parameters

window ([Window](#)) – The input window.

Returns

row_slice, col_slice – A pair of slices in row, column order

Return type

[slice](#)

6.1.3 Module contents

Rasterio

class rasterio.CRS(*initialdata=None, **kwargs*)

Bases: [object](#)

A geographic or projected coordinate reference system.

CRS objects may be created by passing PROJ parameters as keyword arguments to the standard constructor or by passing EPSG codes, PROJ mappings, PROJ strings, or WKT strings to the from_epsg, from_dict, from_string, or from_wkt static methods.

Examples

The from_dict method takes PROJ parameters as keyword arguments.

```
>>> crs = CRS.from_dict(proj="aea")
```

EPSG codes may be used with the from_epsg method.

```
>>> crs = CRS.from_epsg(3005)
```

The from_string method takes a variety of input.

```
>>> crs = CRS.from_string("EPSG:3005")
```

data

A PROJ4 dict representation of the CRS.

static from_authority(auth_name, code)

Make a CRS from an authority name and code.

New in version 1.1.7.

Parameters

- **auth_name** (*str*) – The name of the authority.
- **code** (*int or str*) – The code used by the authority.

Return type

CRS

Raises

CRSError –

static from_dict(initialdata=None, **kwargs)

Make a CRS from a dict of PROJ parameters or PROJ JSON.

Parameters

- **initialdata** (*mapping, optional*) – A dictionary or other mapping
- **kwargs** (*mapping, optional*) – Another mapping. Will be overlaid on the initialdata.

Return type

CRS

Raises

CRSError –

static from_epsg(code)

Make a CRS from an EPSG code.

Parameters

- code** (*int or str*) – An EPSG code. Strings will be converted to integers.

Notes

The input code is not validated against an EPSG database.

Return type

CRS

Raises

CRSError –

static from_proj4(*proj*)

Make a CRS from a PROJ4 string.

Parameters

proj (*str*) – A PROJ4 string like “+proj=longlat …”

Return type

CRS

Raises

CRSError –

static from_string(*value*, *morph_from_esri_dialect=False*)

Make a CRS from an EPSG, PROJ, or WKT string

Parameters

- **value** (*str*) – An EPSG, PROJ, or WKT string.
- **morph_from_esri_dialect** (*bool*, *optional*) – If True, items in the input using Esri’s dialect of WKT will be replaced by OGC standard equivalents.

Return type

CRS

Raises

CRSError –

static from_user_input(*value*, *morph_from_esri_dialect=False*)

Make a CRS from a variety of inputs.

Parameters

- **value** (*object*) – User input of many different kinds.
- **morph_from_esri_dialect** (*bool*, *optional*) – If True, items in the input using Esri’s dialect of WKT will be replaced by OGC standard equivalents.

Return type

CRS

Raises

CRSError –

static from_wkt(*wkt*, *morph_from_esri_dialect=False*)

Make a CRS from a WKT string.

Parameters

- **wkt** (*str*) – A WKT string.
- **morph_from_esri_dialect** (*bool*, *optional*) – If True, items in the input using Esri’s dialect of WKT will be replaced by OGC standard equivalents.

Return type`CRS`**Raises**`CRSError` –**get(*self*, *item*)****is_epsg_code**

Test if the CRS is defined by an EPSG code.

Return type`bool`**is_geographic**

Test if the CRS is a geographic coordinate reference system.

Return type`bool`**Raises**`CRSError` –**is_projected**

Test if the CRS is a projected coordinate reference system.

Return type`bool`**Raises**`CRSError` –**is_valid**

Test that the CRS is a geographic or projected CRS.

Return type`bool`**items(*self*)****linear_units**

Get a short name for the linear units of the CRS.

Returns`units` – “m”, “ft”, etc.**Return type**`str`**Raises**`CRSError` –**linear_units_factor**

Get linear units and the conversion factor to meters of the CRS.

Returns

- `units` (`str`) – “m”, “ft”, etc.
- `factor` (`float`) – Ratio of one unit to one meter.

Raises`CRSError` –

to_authority(*self*, *confidence_threshold*=70)

Convert to the best match authority name and code.

For a CRS created using an EPSG code, that same value is returned. For other CRS, including custom CRS, an attempt is made to match it to definitions in authority files. Matches with a confidence below the threshold are discarded.

Parameters

confidence_threshold (*int*) – Percent match confidence threshold (0-100).

Returns

- **name** (*str*) – Authority name.
- **code** (*str*) – Code from the authority file.
- or *None*

to_dict(*self*, *projjson*=*False*)

Convert CRS to a PROJ dict.

Note: If there is a corresponding EPSG code, it will be used when returning PROJ parameter dict.

New in version 1.3.0.

Parameters

projjson (*bool*, *default=False*) – If True, will convert to PROJ JSON dict (Requires GDAL 3.1+ and PROJ 6.2+). If False, will convert to PROJ parameter dict.

Return type

dict

to_epsg(*self*, *confidence_threshold*=70)

Convert to the best match EPSG code.

For a CRS created using an EPSG code, that same value is returned. For other CRS, including custom CRS, an attempt is made to match it to definitions in the EPSG authority file. Matches with a confidence below the threshold are discarded.

Parameters

confidence_threshold (*int*) – Percent match confidence threshold (0-100).

Return type

int or *None*

Raises

CRSError –

to_proj4(*self*)

Convert to a PROJ4 representation.

Return type

str

to_string(*self*)

Convert to a PROJ4 or WKT string.

The output will be reduced as much as possible by attempting a match to CRS defined in authority files.

Notes

Mapping keys are tested against the `all_proj_keys` list. Values of `True` are omitted, leaving the key bare: `{'no_defs': True}` -> “+no_defs” and items where the value is otherwise not a str, int, or float are omitted.

Return type

`str`

Raises

`CRSError` –

`to_wkt(self, morph_to_esri_dialect=False, version=None)`

Convert to a OGC WKT representation.

New in version 1.3.0: `version`

Parameters

- `morph_to_esri_dialect` (`bool`, *optional*) – Whether or not to morph to the Esri dialect of WKT Only applies to GDAL versions < 3. This parameter will be removed in a future version of rasterio.
- `version` (`WktVersion` or `str`, *optional*) – The version of the WKT output. Only works with GDAL 3+. Default is `WKT1_GDAL`.

Return type

`str`

Raises

`CRSError` –

`units_factor`

Get units and the conversion factor of the CRS.

Returns

- `units` (`str`) – “m”, “ft”, etc.
- `factor` (`float`) – Ratio of one unit to one radian if the CRS is geographic otherwise, it is to one meter.

Raises

`CRSError` –

`wkt`

An OGC WKT representation of the CRS

Return type

`str`

```
class rasterio.Env(session=None, aws_unsigned=False, profile_name=None, session_class=<function Session.aws_or_dummy>, **options)
```

Bases: `object`

Abstraction for GDAL and AWS configuration

The GDAL library is stateful: it has a registry of format drivers, an error stack, and dozens of configuration options.

Rasterio’s approach to working with GDAL is to wrap all the state up using a Python context manager (see PEP 343, <https://www.python.org/dev/peps/pep-0343/>). When the context is entered GDAL drivers are registered,

error handlers are configured, and configuration options are set. When the context is exited, drivers are removed from the registry and other configurations are removed.

Example

```
with rasterio.Env(GDAL_CACHEMAX=128000000) as env:  
    # All drivers are registered, GDAL's raster block cache  
    # size is set to 128 MB.  
    # Commence processing...  
    ...  
    # End of processing.  
  
    # At this point, configuration options are set to their  
    # previous (possible unset) values.
```

A boto3 session or boto3 session constructor arguments `aws_access_key_id`, `aws_secret_access_key`, `aws_session_token` may be passed to Env's constructor. In the latter case, a session will be created as soon as needed. AWS credentials are configured for GDAL as needed.

`credentialize()`

Get credentials and configure GDAL

Note well: this method is a no-op if the GDAL environment already has credentials, unless session is not None.

Return type

`None`

`classmethod default_options()`

Default configuration options

Parameters

`None` –

Return type

`dict`

`drivers()`

Return a mapping of registered drivers.

`classmethod from_defaults(*args, **kwargs)`

Create an environment with default config options

Parameters

- **args** (*optional*) – Positional arguments for `Env()`
- **kwargs** (*optional*) – Keyword arguments for `Env()`

Return type

`Env`

Notes

The items in kwargs will be overlaid on the default values.

rasterio.band(ds, bidx)

A dataset and one or more of its bands

Parameters

- **ds** (*dataset object*) – An opened rasterio dataset object.
- **bidx** (*int or sequence of ints*) – Band number(s), index starting at 1.

Return type

rasterio.Band

rasterio.open(fp, mode='r', driver=None, width=None, height=None, count=None, crs=None, transform=None, dtype=None, nodata=None, sharing=False, **kwargs)

Open a dataset for reading or writing.

The dataset may be located in a local file, in a resource located by a URL, or contained within a stream of bytes.

In read ('r') or read/write ('r+') mode, no keyword arguments are required: these attributes are supplied by the opened dataset.

In write ('w' or 'w+') mode, the driver, width, height, count, and dtype keywords are strictly required.

Parameters

- **fp** (*str, file object, PathLike object, FilePath, or MemoryFile*) – A file-name or URL, a file object opened in binary ('rb') mode, a Path object, or one of the rasterio classes that provides the dataset-opening interface (has an open method that returns a dataset).
- **mode** (*str, optional*) – 'r' (read, the default), 'r+' (read/write), 'w' (write), or 'w+' (write/read).
- **driver** (*str, optional*) – A short format driver name (e.g. "GTiff" or "JPEG") or a list of such names (see GDAL docs at <https://gdal.org/drivers/raster/index.html>). In 'w' or 'w+' modes a single name is required. In 'r' or 'r+' modes the driver can usually be omitted. Registered drivers will be tried sequentially until a match is found. When multiple drivers are available for a format such as JPEG2000, one of them can be selected by using this keyword argument.
- **width** (*int, optional*) – The number of columns of the raster dataset. Required in 'w' or 'w+' modes, it is ignored in 'r' or 'r+' modes.
- **height** (*int, optional*) – The number of rows of the raster dataset. Required in 'w' or 'w+' modes, it is ignored in 'r' or 'r+' modes.
- **count** (*int, optional*) – The count of dataset bands. Required in 'w' or 'w+' modes, it is ignored in 'r' or 'r+' modes.
- **crs** (*str, dict, or CRS; optional*) – The coordinate reference system. Required in 'w' or 'w+' modes, it is ignored in 'r' or 'r+' modes.
- **transform** (*Affine instance, optional*) – Affine transformation mapping the pixel space to geographic space. Required in 'w' or 'w+' modes, it is ignored in 'r' or 'r+' modes.
- **dtype** (*str or numpy dtype*) – The data type for bands. For example: 'uint8' or rasterio.uint16. Required in 'w' or 'w+' modes, it is ignored in 'r' or 'r+' modes.

- **nodata** (*int, float, or nan; optional*) – Defines the pixel value to be interpreted as not valid data. Required in ‘w’ or ‘w+’ modes, it is ignored in ‘r’ or ‘r+’ modes.
- **sharing** (*bool; optional*) – To reduce overhead and prevent programs from running out of file descriptors, rasterio maintains a pool of shared low level dataset handles. When *True* this function will use a shared handle if one is available. Multithreaded programs must avoid sharing and should set *sharing* to *False*.
- **kwargs** (*optional*) – These are passed to format drivers as directives for creating or interpreting datasets. For example: in ‘w’ or ‘w+’ modes a *tiled=True* keyword argument will direct the GeoTIFF format driver to create a tiled, rather than striped, TIFF.

Return type

A DatasetReader or DatasetWriter object.

Examples

To open a GeoTIFF for reading using standard driver discovery and no directives:

```
>>> import rasterio
>>> with rasterio.open('example.tif') as dataset:
...     print(dataset.profile)
```

To open a JPEG2000 using only the JP2OpenJPEG driver:

```
>>> with rasterio.open(
...     'example.jp2', driver='JP2OpenJPEG') as dataset:
...     print(dataset.profile)
```

To create a new 8-band, 16-bit unsigned, tiled, and LZW-compressed GeoTIFF with a global extent and 0.5 degree resolution:

```
>>> from rasterio.transform import from_origin
>>> with rasterio.open(
...     'example.tif', 'w', driver='GTiff', dtype='uint16',
...     width=720, height=360, count=8, crs='EPSG:4326',
...     transform=from_origin(-180.0, 90.0, 0.5, 0.5),
...     nodata=0, tiled=True, compress='lzw') as dataset:
...     dataset.write(...)
```

rasterio.pad(array, transform, pad_width, mode=None, **kwargs)

pad array and adjust affine transform matrix.

Parameters

- **array** (*ndarray*) – Numpy ndarray, for best results a 2D array
- **transform** (*Affine transform*) – transform object mapping pixel space to coordinates
- **pad_width** (*int*) – number of pixels to pad array on all four
- **mode** (*str or function*) – define the method for determining padded values

Returns

(array, transform) – Tuple of new array and affine transform

Return type

tuple

Notes

See numpy docs for details on mode and other kwargs: <http://docs.scipy.org/doc/numpy-1.10.0/reference/generated/numpy.pad.html>

CONTRIBUTING

Welcome to the Rasterio project. Here's how we work.

7.1 Code of Conduct

First of all: the Rasterio project has a code of conduct. Please read the CODE_OF_CONDUCT.txt file, it's important to all of us.

7.2 Rights

The BSD license (see LICENSE.txt) applies to all contributions.

7.3 Issue Conventions

The Rasterio issue tracker is for actionable issues.

Questions about installation, distribution, and usage should be taken to the project's [general discussion group](#). Opened issues which fall into one of these three categories may be perfunctorily closed.

Questions about development of Rasterio, brainstorming, requests for comment, and not-yet-actionable proposals are welcome in the project's [developers discussion group](#). Issues opened in Rasterio's GitHub repo which haven't been socialized there may be perfunctorily closed.

Rasterio is a relatively new project and highly active. We have bugs, both known and unknown.

Please search existing issues, open and closed, before creating a new one.

Rasterio employs C extension modules, so bug reports very often hinge on the following details:

- Operating system type and version (Windows? Ubuntu 20.04? 18.04?)
- The version and source of Rasterio (PyPI, Anaconda, or somewhere else?)
- The version and source of GDAL (UbuntuGIS? Homebrew?)

Please provide these details as well as tracebacks and relevant logs. When using the `$ rio` CLI logging can be enabled with `$ rio -v` and verbosity can be increased with `-vvv`. Short scripts and datasets demonstrating the issue are especially helpful!

7.4 Design Principles

Rasterio's API is both similar to and different from GDAL's API and this is intentional.

- Rasterio is a library for reading and writing raster datasets. Rasterio uses GDAL but is not a “Python binding for GDAL.”
- Rasterio aims to hide, or at least contain, the complexity of GDAL.
- Rasterio always prefers Python's built-in protocols and types or Numpy protocols and types over concepts from GDAL's data model.
- Rasterio keeps I/O separate from other operations. `rasterio.open()` is the only library function that operates on filenames and URIs. `dataset.read()`, `dataset.write()`, and their mask counterparts are the methods that perform I/O.
- Rasterio methods and functions should be free of side-effects and hidden inputs. This is challenging in practice because GDAL embraces global variables.
- Rasterio leans on analogies to other familiar Python APIs.

7.5 Dataset Objects

Our term for the kind of object that allows read and write access to raster data is *dataset object*. A dataset object might be an instance of `DatasetReader` or `DatasetWriter`. The canonical way to create a dataset object is by using the `rasterio.open()` function.

This is analogous to Python's use of `file object`.

7.6 Path Objects

A *path object* specifies the name and address of a dataset within some space (filesystem, internet, cloud) along with optional parameters. The first positional argument of `rasterio.open()` is a path. Some path objects also have an `open` method which can be used to create a dataset object.

7.7 Band Objects

Unlike GDAL's original original data model, rasterio has no band objects. In this way it's more like GDAL's multi-dimensional API. A dataset's `read()` method returns N-D arrays.

7.8 GDAL Context

GDAL depends on some global context: a format driver registry, dataset connection pool, a raster block cache, a file header cache. Rasterio depends on this, too, but unlike GDAL's official Python bindings, delays initializing this context as long as possible and abstracts it with the help of a Python context manager.

7.9 Git Conventions

We use a variant of centralized workflow described in the [Git Book](#). Since Rasterio 1.0 we tag and release versions in the form: *x.y.z* version from the *maint-x.y* branch.

Work on features in a new branch of the mapbox/rasterio repo or in a branch on a fork. Create a [GitHub pull request](#) when the changes are ready for review. We recommend creating a pull request as early as possible to give other developers a heads up and to provide an opportunity for valuable early feedback.

7.10 Conventions

The `rasterio` namespace contains both Python and C extension modules. All C extension modules are written using [Cython](#). The Cython language is a superset of Python. Cython files end with `.pyx` and `.pxd` and are where we keep all the code that calls GDAL's C functions.

Rasterio works with Python versions 3.6 through 3.9.

We strongly prefer code adhering to [PEP8](#).

Tests are mandatory for new code. We use [pytest](#). Use pytest's parameterization feature.

We aspire to 100% coverage for Python modules but coverage of the Cython code is a future aspiration ([#515](#)).

Use [darker](#) to reformat code as you change it. We aren't going to run black on everything all at once.

Type hints are welcome as a part of refactoring work or new feature development. We aren't going to make a large initiative about adding hints to everything.

Changes should be noted in `CHANGES.txt`. New entries go above older entries.

7.11 New Containerized Development Environment

Rasterio has a new Dockerfile that can be used to create images and containers for exploring or testing the package.

The command `make dockertest` will build a Docker image based on one of the official GDAL images, start a container that mounts the working directory, and run `python setup.py develop && python -m pytest` in the container.

7.12 Historical Development Environment

If you prefer not to use the new development environment you may install rasterio's dependencies directly onto your computer.

Developing Rasterio requires Python 3.6 or any final release after and including 3.10. We prefer developing with the most recent version of Python but recognize this is not possible for all contributors. A C compiler is also required to leverage [existing protocols](#) for extending Python with C or C++. See the Windows install instructions in the `readme` for more information about building on Windows.

7.12.1 Initial Setup

First, clone Rasterio's git repo:

```
$ git clone https://github.com/rasterio/rasterio
```

Development should occur within a [virtual environment](#) to better isolate development work from custom environments.

In some cases installing a library with an accompanying executable inside a virtual environment causes the shell to initially look outside the environment for the executable. If this occurs try deactivating and reactivating the environment.

7.12.2 Installing GDAL

The GDAL library and its headers are required to build Rasterio. We do not have currently have guidance for any platforms other than Linux and OS X.

On Linux, GDAL and its headers should be available through your distro's package manager. For Ubuntu the commands are:

```
$ sudo add-apt-repository ppa:ubuntugis/ppa  
$ sudo apt-get update  
$ sudo apt-get install gdal-bin libgdal-dev
```

On OS X, Homebrew is a reliable way to get GDAL.

```
$ brew install gdal
```

7.12.3 Python build requirements

Provision a virtualenv with Rasterio's build requirements. Rasterio's `setup.py` script will not run unless Cython and Numpy are installed, so do this first from the Rasterio repo directory.

Linux users may need to install some additional Numpy dependencies:

```
$ sudo apt-get install libatlas-dev libatlas-base-dev gfortran
```

then:

```
$ pip install -U pip  
$ pip install -r requirements-dev.txt
```

7.12.4 Installing Rasterio

Rasterio, its Cython extensions, normal dependencies, and dev dependencies can be installed with `$ pip`. Installing Rasterio in editable mode while developing is very convenient but only affects the Python files. Specifying the `[test]` extra in the command below tells `$ pip` to also install Rasterio's dev dependencies.

```
$ pip install -e .[test]
```

Any time a Cython (`.pyx` or `.pxd`) file is edited the extension modules need to be recompiled, which is most easily achieved with:

```
$ pip install -e .
```

When switching between Python versions the extension modules must be recompiled, which can be forced with `$ touch rasterio/*.pyx` and then re-installing with the command above. If this is not done an error claiming that an object has the wrong size, try recompiling is raised.

The dependencies required to build the docs can be installed with:

```
$ pip install -e .[docs]
```

7.12.5 Running the tests

Rasterio's tests live in `tests <tests/>` and generally match the main package layout.

To run the entire suite and the code coverage report:

Note: rasterio must be installed in editable mode in order to run tests.

```
$ python -m pytest --cov rasterio --cov-report term-missing
```

A single test file:

```
$ python -m pytest tests/test_band.py
```

A single test:

```
$ python -m pytest tests/test_band.py::test_band
```

7.13 Additional Information

More technical information lives on the wiki.

- <https://github.com/rasterio/rasterio/wiki/Development-Guide>
- <https://github.com/rasterio/rasterio/wiki/Exposing-GDAL-Functionality>
- <https://github.com/rasterio/rasterio/wiki/Cython-and-GDAL>

The long term goal is to consolidate into this document.

FREQUENTLY ASKED QUESTIONS

8.1 Where is “ERROR 4: Unable to open EPSG support file gcs.csv” coming from and what does it mean?

The full message is “ERROR 4: Unable to open EPSG support file gcs.csv. Try setting the GDAL_DATA environment variable to point to the directory containing EPSG csv files.” The GDAL/OGR library prints this text to your process’s stdout stream when it can not find the gcs.csv data file it needs to interpret spatial reference system information stored with a dataset. If you’ve never seen this before, you can summon this message by setting GDAL_DATA to a bogus value in your shell and running a command like ogrinfo:

```
$ GDAL_DATA="/path/to/nowhere" ogrinfo example.shp -so example
INFO: Open of 'example.shp'
      using driver 'ESRI Shapefile' successful.

Layer name: example
Geometry: Polygon
Feature Count: 67
Extent: (-113.564247, 37.068981) - (-104.970871, 41.996277)
ERROR 4: Unable to open EPSG support file gcs.csv. Try setting the GDAL_DATA_
environment variable to point to the directory containing EPSG csv files.
```

If you’re using GDAL software installed by a package management system like apt or yum, or Homebrew, or if you’ve built and installed it using `configure`; `make`; `make install`, you don’t need to set the GDAL_DATA environment variable. That software has the right directory path built in. If you see this error, it’s likely a sign that GDAL_DATA is set to a bogus value. Unset GDAL_DATA if it exists and see if that eliminates the error condition and the message.

Important: Activate your conda environments. The GDAL conda package will set GDAL_DATA to the proper value if you activate your conda environment. If you don’t activate your conda enviornment, you are likely to see the error message shown above.

8.2 Why can't rasterio find proj.db (rasterio versions < 1.2.0)?

If you see `rasterio.errors.CRSError: The EPSG code is unknown.` `PROJ: proj_create_from_database: Cannot find proj.db` it is because the PROJ library (one of rasterio's dependencies) cannot find its database of projections and coordinate systems. In some installations the `PROJ_LIB` (`PROJ < 9.1`) | `PROJ_DATA` (`PROJ 9.1+`) [environment variable must be set](#) for PROJ to work properly.

Important: Activate your conda environments. The PROJ conda package will set `PROJ_LIB` (`PROJ < 9.1`) | `PROJ_DATA` (`PROJ 9.1+`) to the proper value if you activate your conda environment. If you don't activate your conda environment, you are likely to see the exception shown above.

8.3 Why can't rasterio find proj.db (rasterio from PyPI versions >= 1.2.0)?

Starting with version 1.2.0, rasterio wheels on PyPI include PROJ 7.x and GDAL 3.x. The libraries and modules in these wheels are incompatible with older versions of PROJ that may be installed on your system. If `PROJ_LIB` (`PROJ < 9.1`) | `PROJ_DATA` (`PROJ 9.1+`) is set in your program's environment and points to an older version of PROJ, you must unset this variable. Rasterio will then use the version of PROJ contained in the wheel.

**CHAPTER
NINE**

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

r

rasterio, 214
rasterio.control, 101
rasterio.coords, 101
rasterio.crs, 102
rasterio.drivers, 108
rasterio.dtypes, 109
rasterio.enums, 110
rasterio.env, 115
rasterio.errors, 118
rasterio.features, 121
rasterio.fill, 125
rasterio.io, 126
rasterio.mask, 168
rasterio.merge, 169
rasterio.path, 171
rasterio.plot, 171
rasterio.profiles, 173
rasterio.rio, 101
rasterio.rio.blocks, 95
rasterio.rio.bounds, 95
rasterio.rio.calc, 95
rasterio.rio.clip, 95
rasterio.rio.convert, 95
rasterio.rio.edit_info, 96
rasterio.rio.env, 96
rasterio.rio.gcps, 96
rasterio.rio.helpers, 96
rasterio.rio.info, 97
rasterio.rio.insp, 97
rasterio.rio.main, 97
rasterio.rio.mask, 98
rasterio.rio.merge, 98
rasterio.rio.options, 98
rasterio.rio.overview, 100
rasterio.rio.rasterize, 100
rasterio.rio.rm, 100
rasterio.rio.sample, 100
rasterio.rio.shapes, 100
rasterio.rio.stack, 101
rasterio.rio.transform, 101
rasterio.rio.warp, 101

rasterio.rpc, 174
rasterio.sample, 175
rasterio.session, 176
rasterio.shutil, 186
rasterio.tools, 187
rasterio.transform, 187
rasterio.vrt, 191
rasterio.warp, 204
rasterio.windows, 208

INDEX

A

abspath_forward_slashes() (in module rasterio.rio.options), 99
add (rasterio.enums.MergeAlg attribute), 111
adjust_band() (in module rasterio.plot), 171
affine (rasterio.enums.TransformMethod attribute), 114
AffineTransformer (class in rasterio.transform), 187
aligned_target() (in module rasterio.warp), 204
all_handler() (in module rasterio.rio.edit_info), 96
all_valid (rasterio.enums.MaskFlags attribute), 111
alpha (rasterio.enums.ColorInterp attribute), 110
alpha (rasterio.enums.MaskFlags attribute), 111
array_bounds() (in module rasterio.transform), 189
asdict() (rasterio.control.GroundControlPoint method), 101
at_least() (rasterio.env.GDALVersion method), 116
average (rasterio.enums.Resampling attribute), 112, 113
aws_or_dummy() (rasterio.session.AWSsession static method), 176
aws_or_dummy() (rasterio.session.AzureSession static method), 177
aws_or_dummy() (rasterio.session.DummySession static method), 179
aws_or_dummy() (rasterio.session.GSSession static method), 180
aws_or_dummy() (rasterio.session.OSSSession static method), 181
aws_or_dummy() (rasterio.session.Session static method), 183
aws_or_dummy() (rasterio.session.SwiftSession static method), 184
AWSsession (class in rasterio.session), 176
AzureSession (class in rasterio.session), 177

B

band (rasterio.enums.Interleaving attribute), 111
band() (in module rasterio), 221
BandOverviewError, 118
bilinear (rasterio.enums.Resampling attribute), 112, 113
black (rasterio.enums.ColorInterp attribute), 110
black (rasterio.enums.PhotometricInterp attribute), 112

block_shapes (rasterio.io.BufferedDatasetWriter attribute), 126
block_shapes (rasterio.io.DatasetReader attribute), 140
block_shapes (rasterio.io.DatasetWriter attribute), 151
block_shapes (rasterio.vrt.WarpedVRT attribute), 193
block_size() (rasterio.io.BufferedDatasetWriter method), 126
block_size() (rasterio.io.DatasetReader method), 140
block_size() (rasterio.io.DatasetWriter method), 151
block_size() (rasterio.vrt.WarpedVRT method), 193
block_window() (rasterio.io.BufferedDatasetWriter method), 126
block_window() (rasterio.io.DatasetReader method), 140
block_window() (rasterio.io.DatasetWriter method), 152
block_window() (rasterio.vrt.WarpedVRT method), 193
block_windows() (rasterio.io.BufferedDatasetWriter method), 126
block_windows() (rasterio.io.DatasetReader method), 140
block_windows() (rasterio.io.DatasetWriter method), 152
block_windows() (rasterio.vrt.WarpedVRT method), 193
blue (rasterio.enums.ColorInterp attribute), 110
bottom (rasterio.coords.BoundingBox attribute), 101, 102
BoundingBox (class in rasterio.coords), 101
bounds (rasterio.io.BufferedDatasetWriter attribute), 127
bounds (rasterio.io.DatasetReader attribute), 141
bounds (rasterio.io.DatasetWriter attribute), 153
bounds (rasterio.vrt.WarpedVRT attribute), 194
bounds() (in module rasterio.features), 121
bounds() (in module rasterio.windows), 211
bounds_handler() (in module rasterio.rio.options), 99
BufferedDatasetWriter (class in rasterio.io), 126
build_handler() (in module rasterio.rio.overview), 100
build_overviews() (rasterio.io.BufferedDatasetWriter method), 128

`build_overviews()` (*rasterio.io.DatasetWriter method*), 153

C

`calculate_default_transform()` (*in module rasterio.warp*), 204

`can_cast_dtype()` (*in module rasterio.dtypes*), 109

`Cb` (*rasterio.enums.ColorInterp attribute*), 110

`ccittfax3` (*rasterio.enums.Compression attribute*), 110

`ccittfax4` (*rasterio.enums.Compression attribute*), 110

`ccittrle` (*rasterio.enums.Compression attribute*), 111

`check_dtype()` (*in module rasterio.dtypes*), 109

`checksum()` (*rasterio.io.BufferedDatasetWriter method*), 128

`checksum()` (*rasterio.io.DatasetReader method*), 141

`checksum()` (*rasterio.io.DatasetWriter method*), 153

`checksum()` (*rasterio.vrt.WarpedVRT method*), 194

`cielab` (*rasterio.enums.PhotometricInterp attribute*), 112

`close()` (*rasterio.io.BufferedDatasetWriter method*), 128

`close()` (*rasterio.io.DatasetReader method*), 141

`close()` (*rasterio.io.DatasetWriter method*), 153

`close()` (*rasterio.io.MemoryFile method*), 165

`close()` (*rasterio.io.ZipMemoryFile method*), 166

`close()` (*rasterio.transform.GDALTransformerBase method*), 187

`close()` (*rasterio.vrt.WarpedVRT method*), 195

`closed` (*rasterio.io.BufferedDatasetWriter attribute*), 128

`closed` (*rasterio.io.DatasetReader attribute*), 141

`closed` (*rasterio.io.DatasetWriter attribute*), 153

`closed` (*rasterio.vrt.WarpedVRT attribute*), 195

`cls_from_path()` (*rasterio.session.AWSsession static method*), 176

`cls_from_path()` (*rasterio.session.AzureSession static method*), 177

`cls_from_path()` (*rasterio.session.DummySession static method*), 179

`cls_from_path()` (*rasterio.session.GSSession static method*), 180

`cls_from_path()` (*rasterio.session.OSSSession static method*), 182

`cls_from_path()` (*rasterio.session.Session static method*), 183

`cls_from_path()` (*rasterio.session.SwiftSession static method*), 185

`cmyk` (*rasterio.enums.PhotometricInterp attribute*), 112

`col_off` (*rasterio.windows.Window attribute*), 209

`ColorInterp` (*class in rasterio.enums*), 110

`colorinterp` (*rasterio.io.BufferedDatasetWriter attribute*), 128

`colorinterp` (*rasterio.io.DatasetReader attribute*), 142

`colorinterp` (*rasterio.io.DatasetWriter attribute*), 153

`colorinterp` (*rasterio.vrt.WarpedVRT attribute*), 195

`colorinterp_handler()` (*in module rasterio.rio.edit_info*), 96

`colormap()` (*rasterio.io.BufferedDatasetWriter method*), 128

`colormap()` (*rasterio.io.DatasetReader method*), 142

`colormap()` (*rasterio.io.DatasetWriter method*), 153

`colormap()` (*rasterio.vrt.WarpedVRT method*), 195

`Compression` (*class in rasterio.enums*), 110

`compression` (*rasterio.io.BufferedDatasetWriter attribute*), 128

`compression` (*rasterio.io.DatasetReader attribute*), 142

`compression` (*rasterio.io.DatasetWriter attribute*), 154

`compression` (*rasterio.vrt.WarpedVRT attribute*), 195

`configure_logging()` (*in module rasterio.rio.main*), 98

`coords()` (*in module rasterio.rio.helpers*), 96

`copy()` (*in module rasterio.shutil*), 186

`copy_count()` (*in module rasterio.merge*), 169

`copy_first()` (*in module rasterio.merge*), 169

`copy_last()` (*in module rasterio.merge*), 169

`copy_max()` (*in module rasterio.merge*), 170

`copy_min()` (*in module rasterio.merge*), 170

`copy_sum()` (*in module rasterio.merge*), 170

`copyfiles()` (*in module rasterio.shutil*), 186

`count` (*rasterio.io.BufferedDatasetWriter attribute*), 128

`count` (*rasterio.io.DatasetReader attribute*), 142

`count` (*rasterio.io.DatasetWriter attribute*), 154

`count` (*rasterio.vrt.WarpedVRT attribute*), 195

`Cr` (*rasterio.enums.ColorInterp attribute*), 110

`credentialize()` (*rasterio.Env method*), 220

`credentialize()` (*rasterio.env.Env method*), 115

`credentials` (*rasterio.session.AWSsession property*), 176

`credentials` (*rasterio.session.AzureSession property*), 178

`credentials` (*rasterio.session.DummySession attribute*), 179

`credentials` (*rasterio.session.GSSession property*), 180

`credentials` (*rasterio.session.OSSSession property*), 182

`credentials` (*rasterio.session.Session attribute*), 183

`credentials` (*rasterio.session.SwiftSession property*), 185

`crop()` (*in module rasterio.windows*), 211

`crop()` (*rasterio.windows.Window method*), 209

`CRS` (*class in rasterio*), 214

`CRS` (*class in rasterio.crs*), 102

`crs` (*rasterio.io.BufferedDatasetWriter attribute*), 128

`crs` (*rasterio.io.DatasetReader attribute*), 142

`crs` (*rasterio.io.DatasetWriter attribute*), 154

`crs` (*rasterio.vrt.WarpedVRT attribute*), 195

`crs_handler()` (*in module rasterio.rio.edit_info*), 96

`CRSError`, 118

`cubic` (*rasterio.enums.Resampling attribute*), 112, 113

cubic_spline (*rasterio.enums.Resampling attribute*), 112, 113
cyan (*rasterio.enums.ColorInterp attribute*), 110

D

data (*rasterio.CRS attribute*), 215
data (*rasterio.crs.CRS attribute*), 103
dataset_features() (*in module rasterio.features*), 121
dataset_mask() (*rasterio.io.BufferedDatasetWriter method*), 129
dataset_mask() (*rasterio.io.DatasetReader method*), 142
dataset_mask() (*rasterio.io.DatasetWriter method*), 154
dataset_mask() (*rasterio.vrt.WarpedVRT method*), 195
DatasetAttributeError, 118
DatasetIOSError, 118
DatasetReader (*class in rasterio.io*), 139
DatasetWriter (*class in rasterio.io*), 151
default_options() (*rasterio.Env class method*), 220
default_options() (*rasterio.env.Env class method*), 115
DefaultGTiffProfile (*class in rasterio.profiles*), 173
defaults (*rasterio.profiles.DefaultGTiffProfile attribute*), 173
defaults (*rasterio.profiles.Profile attribute*), 174
defenv() (*in module rasterio.env*), 116
deflate (*rasterio.enums.Compression attribute*), 111
delenv() (*in module rasterio.env*), 116
delete() (*in module rasterio.shutil*), 186
deprecated_precision() (*in module rasterio.rio.merge*), 98
descriptions (*rasterio.io.BufferedDatasetWriter attribute*), 129
descriptions (*rasterio.io.DatasetReader attribute*), 143
descriptions (*rasterio.io.DatasetWriter attribute*), 155
descriptions (*rasterio.vrt.WarpedVRT attribute*), 196
disjoint_bounds() (*in module rasterio.coords*), 102
driver (*rasterio.io.BufferedDatasetWriter attribute*), 130
driver (*rasterio.io.DatasetReader attribute*), 143
driver (*rasterio.io.DatasetWriter attribute*), 155
driver (*rasterio.vrt.WarpedVRT attribute*), 196
driver_from_extension() (*in module rasterio.drivers*), 108
DriverCapabilityError, 118
DriverRegistrationError, 118
drivers() (*rasterio.Env method*), 220
drivers() (*rasterio.env.Env method*), 115
dst_nodata (*rasterio.vrt.WarpedVRT attribute*), 192
dtypes (*rasterio.io.BufferedDatasetWriter attribute*), 130
dtypes (*rasterio.io.DatasetReader attribute*), 143
dtypes (*rasterio.io.DatasetWriter attribute*), 155
dtypes (*rasterio.vrt.WarpedVRT attribute*), 196

DummySession (*class in rasterio.session*), 179

E

edit_nodata_handler() (*in module rasterio.rio.options*), 99
ensure_env() (*in module rasterio.env*), 116
ensure_env_credentialled() (*in module rasterio.env*), 116
ensure_env_with_credentials() (*in module rasterio.env*), 116
Env (*class in rasterio*), 219
Env (*class in rasterio.env*), 115
env_ctx_if_needed() (*in module rasterio.env*), 117
EnvError, 118
epsg_treats_as_latlong() (*in module rasterio.crs*), 107
epsg_treats_as_northingeasting() (*in module rasterio.crs*), 108
err_bias (*rasterio.rpc.RPC attribute*), 174
err_rand (*rasterio.rpc.RPC attribute*), 174
evaluate() (*in module rasterio.windows*), 212
exists() (*in module rasterio.shutil*), 186
exists() (*rasterio.io.MemoryFile method*), 165
exists() (*rasterio.io.ZipMemoryFile method*), 166

F

feature_gen() (*in module rasterio.rio.shapes*), 100
file_in_handler() (*in module rasterio.rio.options*), 99
FileOverwriteError, 118
FilePath (*in module rasterio.io*), 165
files (*rasterio.io.BufferedDatasetWriter attribute*), 130
files (*rasterio.io.DatasetReader attribute*), 143
files (*rasterio.io.DatasetWriter attribute*), 155
files (*rasterio.vrt.WarpedVRT attribute*), 196
files_handler() (*in module rasterio.rio.rasterize*), 100
files_in_handler() (*in module rasterio.rio.options*), 99
files_inout_handler() (*in module rasterio.rio.options*), 99
fillnodata() (*in module rasterio.fill*), 125
flatten() (*rasterio.windows.Window method*), 209
forward (*rasterio.enums.TransformDirection attribute*), 114
from_authority() (*rasterio.CRS static method*), 215
from_authority() (*rasterio.crs.CRS static method*), 103
from_bounds() (*in module rasterio.transform*), 189
from_bounds() (*in module rasterio.windows*), 212
from_defaults() (*rasterio.Env class method*), 220
from_defaults() (*rasterio.env.Env class method*), 115
from_dict() (*rasterio.CRS static method*), 215
from_dict() (*rasterio.crs.CRS static method*), 103
from_environ() (*rasterio.session.AWSsession static method*), 176

`from_environ()` (*rasterio.session.AzureSession static method*), 178
`from_environ()` (*rasterio.session.DummySession static method*), 179
`from_environ()` (*rasterio.session.GSSession static method*), 180
`from_environ()` (*rasterio.session.OSSSession static method*), 182
`from_environ()` (*rasterio.session.Session static method*), 183
`from_environ()` (*rasterio.session.SwiftSession static method*), 185
`from_epsg()` (*rasterio.CRS static method*), 215
`from_epsg()` (*rasterio.crs.CRS static method*), 103
`from_foreign_session()` (*rasterio.session.AWSsession static method*), 176
`from_foreign_session()` (*rasterio.session.AzureSession static method*), 178
`from_foreign_session()` (*rasterio.session.DummySession static method*), 179
`from_foreign_session()` (*rasterio.session.GSSession static method*), 181
`from_foreign_session()` (*rasterio.session.OSSSession static method*), 182
`from_foreign_session()` (*rasterio.session.Session static method*), 184
`from_foreign_session()` (*rasterio.session.SwiftSession static method*), 185
`from_gcps()` (*in module rasterio.transform*), 189
`from_gdal()` (*rasterio.rpc.RPC class method*), 175
`from_like_context()` (*in module rasterio.rio.options*), 99
`from_origin()` (*in module rasterio.transform*), 190
`from_path()` (*rasterio.session.AWSsession static method*), 177
`from_path()` (*rasterio.session.AzureSession static method*), 178
`from_path()` (*rasterio.session.DummySession static method*), 179
`from_path()` (*rasterio.session.GSSession static method*), 181
`from_path()` (*rasterio.session.OSSSession static method*), 182
`from_path()` (*rasterio.session.Session static method*), 184
`from_path()` (*rasterio.session.SwiftSession static method*), 185
`from_proj4()` (*rasterio.CRS static method*), 216
`from_proj4()` (*rasterio.crs.CRS static method*), 104
`from_slices()` (*rasterio.windows.Window class method*), 209
`from_string()` (*rasterio.CRS static method*), 216
`from_string()` (*rasterio.crs.CRS static method*), 104
`from_user_input()` (*rasterio.CRS static method*), 216
`from_user_input()` (*rasterio.crs.CRS static method*), 104
G
`gauss` (*rasterio.enums.Resampling attribute*), 112, 113
`gcps` (*rasterio.enums.TransformMethod attribute*), 114
`gcps` (*rasterio.io.BufferedDatasetWriter attribute*), 130
`gcps` (*rasterio.io.DatasetReader attribute*), 143
`gcps` (*rasterio.io.DatasetWriter attribute*), 155
`gcps` (*rasterio.vrt.WarpedVRT attribute*), 197
`GCPTTransformer` (*class in rasterio.transform*), 187
`gdal_version_cb()` (*in module rasterio.rio.main*), 98
`GDALBehaviorChangeException`, 118
`GDALOptionNotImplementedError`, 119
`GDALTransformerBase` (*class in rasterio.transform*), 187
`GDALVersion` (*class in rasterio.env*), 116
`GDALVersionError`, 119
`geometry_mask()` (*in module rasterio.features*), 121
`geometry_window()` (*in module rasterio.features*), 122
`get()` (*rasterio.CRS method*), 217
`get()` (*rasterio.crs.CRS method*), 105
`get_credential_options()` (*rasterio.session.AWSsession method*), 177
`get_credential_options()` (*rasterio.session.AzureSession method*), 178
`get_credential_options()` (*rasterio.session.DummySession method*), 180
`get_credential_options()` (*rasterio.session.GSSession method*), 181
`get_credential_options()` (*rasterio.session.OSSSession method*), 182
`get_credential_options()` (*rasterio.session.Session method*), 184
`get_credential_options()` (*rasterio.session.SwiftSession method*), 185
`get_data_window()` (*in module rasterio.windows*), 212
`get_gcps()` (*rasterio.io.BufferedDatasetWriter method*), 130
`get_gcps()` (*rasterio.io.DatasetReader method*), 144
`get_gcps()` (*rasterio.io.DatasetWriter method*), 155
`get_gcps()` (*rasterio.vrt.WarpedVRT method*), 197
`get_maximum_overview_level()` (*in module rasterio.rio.overview*), 100
`get_minimum_dtype()` (*in module rasterio.dtypes*), 109
`get_nodatavals()` (*rasterio.io.BufferedDatasetWriter method*), 130
`get_nodatavals()` (*rasterio.io.DatasetReader method*), 144

`get_nodatavals()` (*rasterio.io.DatasetWriter method*), 155
`get_nodatavals()` (*rasterio.vrt.WarpedVRT method*), 197
`get_plt()` (*in module rasterio.plot*), 172
`get_tag_item()` (*rasterio.io.BufferedDatasetWriter method*), 130
`get_tag_item()` (*rasterio.io.DatasetReader method*), 144
`get_tag_item()` (*rasterio.io.DatasetWriter method*), 155
`get_tag_item()` (*rasterio.vrt.WarpedVRT method*), 197
`get_transform()` (*rasterio.io.BufferedDatasetWriter method*), 130
`get_transform()` (*rasterio.io.DatasetReader method*), 144
`get_transform()` (*rasterio.io.DatasetWriter method*), 156
`get_transform()` (*rasterio.vrt.WarpedVRT method*), 197
`get_transformer()` (*in module rasterio.transform*), 190
`get_writer_for_driver()` (*in module rasterio.io*), 167
`get_writer_for_path()` (*in module rasterio.io*), 167
`getbuffer()` (*rasterio.io.MemoryFile method*), 165
`getbuffer()` (*rasterio.io.ZipMemoryFile method*), 166
`getenv()` (*in module rasterio.env*), 117
`gray` (*rasterio.enums.ColorInterp attribute*), 110
`green` (*rasterio.enums.ColorInterp attribute*), 110
`grey` (*rasterio.enums.ColorInterp attribute*), 110
`GroundControlPoint` (*class in rasterio.control*), 101
`GSSession` (*class in rasterio.session*), 180
`guard_transform()` (*in module rasterio.transform*), 190

H

`hascreds()` (*in module rasterio.env*), 117
`hascreds()` (*rasterio.session.AWSsession class method*), 177
`hascreds()` (*rasterio.session.AzureSession class method*), 178
`hascreds()` (*rasterio.session.DummySession class method*), 180
`hascreds()` (*rasterio.session.GSSession class method*), 181
`hascreds()` (*rasterio.session.OSSSession class method*), 183
`hascreds()` (*rasterio.session.Session class method*), 184
`hascreds()` (*rasterio.session.SwiftSession class method*), 185
`hasenv()` (*in module rasterio.env*), 117
`height` (*in module rasterio.rio.overview*), 100
`height` (*rasterio.io.BufferedDatasetWriter attribute*), 130
`height` (*rasterio.io.DatasetReader attribute*), 144
`height` (*rasterio.io.DatasetWriter attribute*), 156
`height` (*rasterio.vrt.WarpedVRT attribute*), 197
`height` (*rasterio.windows.Window attribute*), 209
`height_off` (*rasterio.rpc.RPC attribute*), 175
`height_scale` (*rasterio.rpc.RPC attribute*), 175
`hue` (*rasterio.enums.ColorInterp attribute*), 110

|

`icclab` (*rasterio.enums.PhotometricInterp attribute*), 112
`in_dtype_range()` (*in module rasterio.dtypes*), 109
`index()` (*rasterio.io.BufferedDatasetWriter method*), 130
`index()` (*rasterio.io.DatasetReader method*), 144
`index()` (*rasterio.io.DatasetWriter method*), 156
`index()` (*rasterio.transform.TransformMethodsMixin method*), 187
`index()` (*rasterio.vrt.WarpedVRT method*), 197
`indexes` (*rasterio.io.BufferedDatasetWriter attribute*), 131
`indexes` (*rasterio.io.DatasetReader attribute*), 145
`indexes` (*rasterio.io.DatasetWriter attribute*), 156
`indexes` (*rasterio.vrt.WarpedVRT attribute*), 198
`Interleaving` (*class in rasterio.enums*), 111
`interleaving` (*rasterio.io.BufferedDatasetWriter attribute*), 131
`interleaving` (*rasterio.io.DatasetReader attribute*), 145
`interleaving` (*rasterio.io.DatasetWriter attribute*), 156
`interleaving` (*rasterio.vrt.WarpedVRT attribute*), 198
`intersect()` (*in module rasterio.windows*), 213
`intersection()` (*in module rasterio.windows*), 213
`intersection()` (*rasterio.windows.Window method*), 209
`InvalidArrayError`, 119
`is_blacklisted()` (*in module rasterio.drivers*), 108
`is_epsg_code` (*rasterio.CRS attribute*), 217
`is_epsg_code` (*rasterio.crs.CRS attribute*), 105
`is_geographic` (*rasterio.CRS attribute*), 217
`is_geographic` (*rasterio.crs.CRS attribute*), 105
`is_ndarray()` (*in module rasterio.dtypes*), 109
`is_projected` (*rasterio.CRS attribute*), 217
`is_projected` (*rasterio.crs.CRS attribute*), 105
`is_tiled` (*rasterio.io.BufferedDatasetWriter attribute*), 131
`is_tiled` (*rasterio.io.DatasetReader attribute*), 145
`is_tiled` (*rasterio.io.DatasetWriter attribute*), 156
`is_tiled` (*rasterio.vrt.WarpedVRT attribute*), 198
`is_valid` (*rasterio.CRS attribute*), 217
`is_valid` (*rasterio.crs.CRS attribute*), 105
`is_valid_geom()` (*in module rasterio.features*), 122
`items()` (*rasterio.CRS method*), 217
`items()` (*rasterio.crs.CRS method*), 105

`iter_args()` (*in module rasterio.windows*), 213
`itulab` (*rasterio.enums.PhotometricInterp attribute*), 112

J

`jpeg` (*rasterio.enums.Compression attribute*), 111
`jpeg2000` (*rasterio.enums.Compression attribute*), 111
`JSONSequenceTool` (*class in rasterio.tools*), 187

L

`lanczos` (*rasterio.enums.Resampling attribute*), 112, 113
`lat_off` (*rasterio.rpc.RPC attribute*), 175
`lat_scale` (*rasterio.rpc.RPC attribute*), 175
`left` (*rasterio.coords.BoundingBox attribute*), 101, 102
`lerc` (*rasterio.enums.Compression attribute*), 111
`lerc_deflate` (*rasterio.enums.Compression attribute*), 111
`lerc_zstd` (*rasterio.enums.Compression attribute*), 111
`lightness` (*rasterio.enums.ColorInterp attribute*), 110
`like_handler()` (*in module rasterio.rio.options*), 99
`line` (*rasterio.enums.Interleaving attribute*), 111
`line_den_coeff` (*rasterio.rpc.RPC attribute*), 175
`line_num_coeff` (*rasterio.rpc.RPC attribute*), 175
`line_off` (*rasterio.rpc.RPC attribute*), 175
`line_scale` (*rasterio.rpc.RPC attribute*), 175
`linear_units` (*rasterio.CRS attribute*), 217
`linear_units` (*rasterio.crs.CRS attribute*), 105
`linear_units_factor` (*rasterio.CRS attribute*), 217
`linear_units_factor` (*rasterio.crs.CRS attribute*), 105
`lnglat()` (*rasterio.io.BufferedDatasetWriter method*), 131
`lnglat()` (*rasterio.io.DatasetReader method*), 145
`lnglat()` (*rasterio.io.DatasetWriter method*), 156
`lnglat()` (*rasterio.vrt.WarpedVRT method*), 198
`long_off` (*rasterio.rpc.RPC attribute*), 175
`long_scale` (*rasterio.rpc.RPC attribute*), 175
`lzma` (*rasterio.enums.Compression attribute*), 111
`lzw` (*rasterio.enums.Compression attribute*), 111

M

`magenta` (*rasterio.enums.ColorInterp attribute*), 110
`main()` (*in module rasterio.rio.insp*), 97
`major` (*rasterio.env.GDALVersion attribute*), 116
`mask()` (*in module rasterio.mask*), 168
`mask_flagEnums` (*rasterio.io.BufferedDatasetWriter attribute*), 131
`mask_flagEnums` (*rasterio.io.DatasetReader attribute*), 145
`mask_flagEnums` (*rasterio.io.DatasetWriter attribute*), 157
`mask_flagEnums` (*rasterio.vrt.WarpedVRT attribute*), 198
`MaskFlags` (*class in rasterio.enums*), 111
`max` (*rasterio.enums.Resampling attribute*), 112, 113
`max` (*rasterio.rio.insp.Stats attribute*), 97
`mean` (*rasterio.rio.insp.Stats attribute*), 97
`med` (*rasterio.enums.Resampling attribute*), 112, 113
`MemoryFile` (*class in rasterio.io*), 165
`merge()` (*in module rasterio.merge*), 170
`MergeAlg` (*class in rasterio.enums*), 111
`meta` (*rasterio.io.BufferedDatasetWriter attribute*), 132
`meta` (*rasterio.io.DatasetReader attribute*), 145
`meta` (*rasterio.io.DatasetWriter attribute*), 157
`meta` (*rasterio.vrt.WarpedVRT attribute*), 198
`min` (*rasterio.enums.Resampling attribute*), 112, 113
`min` (*rasterio.rio.insp.Stats attribute*), 97
`minor` (*rasterio.env.GDALVersion attribute*), 116
`minsize` (*in module rasterio.rio.overview*), 100
`mode` (*rasterio.enums.Resampling attribute*), 112, 113
`mode` (*rasterio.io.BufferedDatasetWriter attribute*), 132
`mode` (*rasterio.io.DatasetReader attribute*), 145
`mode` (*rasterio.io.DatasetWriter attribute*), 157
`mode` (*rasterio.vrt.WarpedVRT attribute*), 198
`module`

- `rasterio`, 214
- `rasterio.control`, 101
- `rasterio.coords`, 101
- `rasterio.crs`, 102
- `rasterio.drivers`, 108
- `rasterio.dtypes`, 109
- `rasterio.enums`, 110
- `rasterio.env`, 115
- `rasterio.errors`, 118
- `rasterio.features`, 121
- `rasterio.fill`, 125
- `rasterio.io`, 126
- `rasterio.mask`, 168
- `rasterio.merge`, 169
- `rasterio.path`, 171
- `rasterio.plot`, 171
- `rasterio.profiles`, 173
- `rasterio.rio`, 101
- `rasterio.rio.blocks`, 95
- `rasterio.rio.bounds`, 95
- `rasterio.rio.calc`, 95
- `rasterio.rio.clip`, 95
- `rasterio.rio.convert`, 95
- `rasterio.rio.edit_info`, 96
- `rasterio.rio.env`, 96
- `rasterio.rio.gcps`, 96
- `rasterio.rio.helpers`, 96
- `rasterio.rio.info`, 97
- `rasterio.rio.insp`, 97
- `rasterio.rio.main`, 97
- `rasterio.rio.mask`, 98
- `rasterio.rio.merge`, 98
- `rasterio.rio.options`, 98
- `rasterio.rio.overview`, 100

rasterio.rio.rasterize, 100
 rasterio.rio.rm, 100
 rasterio.rio.sample, 100
 rasterio.rio.shapes, 100
 rasterio.rio.stack, 101
 rasterio.rio.transform, 101
 rasterio.rio.warp, 101
 rasterio.rpc, 174
 rasterio.sample, 175
 rasterio.session, 176
 rasterio.shutil, 186
 rasterio.tools, 187
 rasterio.transform, 187
 rasterio.vrt, 191
 rasterio.warp, 204
 rasterio.windows, 208

N

name (*rasterio.io.BufferedDatasetWriter attribute*), 132
 name (*rasterio.io.DatasetReader attribute*), 145
 name (*rasterio.io.DatasetWriter attribute*), 157
 name (*rasterio.vrt.WarpedVRT attribute*), 199
 nearest (*rasterio.enums.Resampling attribute*), 112, 113
 nodata (*rasterio.enums.MaskFlags attribute*), 111
 nodata (*rasterio.io.BufferedDatasetWriter attribute*), 132
 nodata (*rasterio.io.DatasetReader attribute*), 145
 nodata (*rasterio.io.DatasetWriter attribute*), 157
 nodata (*rasterio.vrt.WarpedVRT attribute*), 199
 nodata_handler() (*in module rasterio.rio.options*), 99
 NodataShadowWarning, 119
 nodatavals (*rasterio.io.BufferedDatasetWriter attribute*), 132
 nodatavals (*rasterio.io.DatasetReader attribute*), 146
 nodatavals (*rasterio.io.DatasetWriter attribute*), 157
 nodatavals (*rasterio.vrt.WarpedVRT attribute*), 199
 none (*rasterio.enums.Compression attribute*), 111
 NotGeoreferencedWarning, 119
 NullContextManager (*class in rasterio.env*), 116

O

offsets (*rasterio.io.BufferedDatasetWriter attribute*), 132
 offsets (*rasterio.io.DatasetReader attribute*), 146
 offsets (*rasterio.io.DatasetWriter attribute*), 158
 offsets (*rasterio.vrt.WarpedVRT attribute*), 199
 open() (*in module rasterio*), 221
 open() (*rasterio.io.MemoryFile method*), 165
 open() (*rasterio.io.ZipMemoryFile method*), 167
 options (*rasterio.io.BufferedDatasetWriter attribute*), 132
 options (*rasterio.io.DatasetReader attribute*), 146
 options (*rasterio.io.DatasetWriter attribute*), 158
 options (*rasterio.vrt.WarpedVRT attribute*), 199
 OSSSession (*class in rasterio.session*), 181

OverviewCreationError, 119
 overviews() (*rasterio.io.BufferedDatasetWriter method*), 132
 overviews() (*rasterio.io.DatasetReader method*), 146
 overviews() (*rasterio.io.DatasetWriter method*), 158
 overviews() (*rasterio.vrt.WarpedVRT method*), 199

P

packbits (*rasterio.enums.Compression attribute*), 111
 pad() (*in module rasterio*), 222
 palette (*rasterio.enums.ColorInterp attribute*), 110
 parse() (*rasterio.env.GDALVersion class method*), 116
 parse_bool() (*in module rasterio.session*), 186
 PathError, 119
 per_dataset (*rasterio.enums.MaskFlags attribute*), 111
 photometric (*rasterio.io.BufferedDatasetWriter attribute*), 132
 photometric (*rasterio.io.DatasetReader attribute*), 146
 photometric (*rasterio.io.DatasetWriter attribute*), 158
 photometric (*rasterio.vrt.WarpedVRT attribute*), 199
 PhotometricInterp (*class in rasterio.enums*), 111
 pixel (*rasterio.enums.Interleaving attribute*), 111
 plotting_extent() (*in module rasterio.plot*), 172
 Profile (*class in rasterio.profiles*), 173
 profile (*rasterio.io.BufferedDatasetWriter attribute*), 132
 profile (*rasterio.io.DatasetReader attribute*), 146
 profile (*rasterio.io.DatasetWriter attribute*), 158
 profile (*rasterio.vrt.WarpedVRT attribute*), 199

Q

q1 (*rasterio.enums.Resampling attribute*), 113
 q3 (*rasterio.enums.Resampling attribute*), 113

R

raster_driver_extensions() (*in module rasterio.drivers*), 109
 raster_geometry_mask() (*in module rasterio.mask*), 168
 RasterBlockError, 119
 rasterio
 module, 214
 rasterio.control
 module, 101
 rasterio.coords
 module, 101
 rasterio.crs
 module, 102
 rasterio.drivers
 module, 108
 rasterio.dtypes
 module, 109
 rasterio.enums

module, 110
rasterio.env
 module, 115
rasterio.errors
 module, 118
rasterio.features
 module, 121
rasterio.fill
 module, 125
rasterio.io
 module, 126
rasterio.mask
 module, 168
rasterio.merge
 module, 169
rasterio.path
 module, 171
rasterio.plot
 module, 171
rasterio.profiles
 module, 173
rasterio.rio
 module, 101
rasterio.rio.blocks
 module, 95
rasterio.rio.bounds
 module, 95
rasterio.rio.calc
 module, 95
rasterio.rio.clip
 module, 95
rasterio.rio.convert
 module, 95
rasterio.rio.edit_info
 module, 96
rasterio.rio.env
 module, 96
rasterio.rio.gcps
 module, 96
rasterio.rio.helpers
 module, 96
rasterio.rio.info
 module, 97
rasterio.rio.insp
 module, 97
rasterio.rio.main
 module, 97
rasterio.rio.mask
 module, 98
rasterio.rio.merge
 module, 98
rasterio.rio.options
 module, 98
rasterio.rio.overview
 module, 100
rasterio.rio.rasterize
 module, 100
rasterio.rio.rm
 module, 100
rasterio.rio.sample
 module, 100
rasterio.rio.shapes
 module, 100
rasterio.rio.stack
 module, 101
rasterio.rio.transform
 module, 101
rasterio.rio.warp
 module, 101
rasterio.rpc
 module, 174
rasterio.sample
 module, 175
rasterio.session
 module, 176
rasterio.shutil
 module, 186
rasterio.tools
 module, 187
rasterio.transform
 module, 187
rasterio.vrt
 module, 191
rasterio.warp
 module, 204
rasterio.windows
 module, 208
RasterioDeprecationWarning, 119
RasterioError, 119
RasterIOError, 120
 rasterize() (in module rasterio.features), 123
read() (rasterio.io.BufferedDatasetWriter method), 132
read() (rasterio.io.DatasetReader method), 146
read() (rasterio.io.DatasetWriter method), 158
read() (rasterio.io.MemoryFile method), 166
read() (rasterio.io.ZipMemoryFile method), 167
read() (rasterio.vrt.WarpedVRT method), 199
read_crs() (rasterio.io.BufferedDatasetWriter method), 134
read_crs() (rasterio.io.DatasetReader method), 147
read_crs() (rasterio.io.DatasetWriter method), 159
read_crs() (rasterio.vrt.WarpedVRT method), 200
read_masks() (rasterio.io.BufferedDatasetWriter method), 134
read_masks() (rasterio.io.DatasetReader method), 147
read_masks() (rasterio.io.DatasetWriter method), 159
read_masks() (rasterio.vrt.WarpedVRT method), 200

`read_transform()` (*rasterio.io.BufferedDatasetWriter method*), 135
`read_transform()` (*rasterio.io.DatasetReader method*), 148
`read_transform()` (*rasterio.io.DatasetWriter method*), 160
`read_transform()` (*rasterio.vrt.WarpedVRT method*), 200
`red` (*rasterio.enums.ColorInterp attribute*), 110
`replace` (*rasterio.enums.MergeAlg attribute*), 111
`reproject()` (*in module rasterio.warp*), 205
`require_gdal_version()` (*in module rasterio.env*), 117
`res` (*rasterio.io.BufferedDatasetWriter attribute*), 135
`res` (*rasterio.io.DatasetReader attribute*), 148
`res` (*rasterio.io.DatasetWriter attribute*), 160
`res` (*rasterio.vrt.WarpedVRT attribute*), 200
`Resampling` (*class in rasterio.enums*), 112
`resampling` (*rasterio.vrt.WarpedVRT attribute*), 192
`ResamplingAlgorithmError`, 120
`reshape_as_image()` (*in module rasterio.plot*), 172
`reshape_as_raster()` (*in module rasterio.plot*), 172
`resolve_inout()` (*in module rasterio.rio.helpers*), 96
`reverse` (*rasterio.enums.TransformDirection attribute*), 114
`rgb` (*rasterio.enums.PhotometricInterp attribute*), 112
`right` (*rasterio.coords.BoundingBox attribute*), 101, 102
`rms` (*rasterio.enums.Resampling attribute*), 113
`round_lengths()` (*rasterio.windows.Window method*), 209
`round_offsets()` (*rasterio.windows.Window method*), 210
`round_shape()` (*rasterio.windows.Window method*), 210
`round_window_to_full_blocks()` (*in module rasterio.windows*), 213
`row_off` (*rasterio.windows.Window attribute*), 210
`rowcol()` (*in module rasterio.transform*), 190
`rowcol()` (*rasterio.transform.TransformerBase method*), 189
`RPC` (*class in rasterio.rpc*), 174
`RPCError`, 119
`rpcs` (*rasterio.enums.TransformMethod attribute*), 114
`rpcs` (*rasterio.io.BufferedDatasetWriter attribute*), 135
`rpcs` (*rasterio.io.DatasetReader attribute*), 148
`rpcs` (*rasterio.io.DatasetWriter attribute*), 160
`rpcs` (*rasterio.vrt.WarpedVRT attribute*), 200
`RPCTransformer` (*class in rasterio.transform*), 187
`runtime()` (*rasterio.env.GDALVersion class method*), 116
`samp_den_coeff` (*rasterio.rpc.RPC attribute*), 175
`samp_num_coeff` (*rasterio.rpc.RPC attribute*), 175
`samp_off` (*rasterio.rpc.RPC attribute*), 175
`samp_scale` (*rasterio.rpc.RPC attribute*), 175
`sample()` (*rasterio.io.BufferedDatasetWriter method*), 135
`sample()` (*rasterio.io.DatasetReader method*), 148
`sample()` (*rasterio.io.DatasetWriter method*), 160
`sample()` (*rasterio.vrt.WarpedVRT method*), 200
`sample_gen()` (*in module rasterio.sample*), 175
`saturation` (*rasterio.enums.ColorInterp attribute*), 110
`scales` (*rasterio.io.BufferedDatasetWriter attribute*), 135
`scales` (*rasterio.io.DatasetReader attribute*), 149
`scales` (*rasterio.io.DatasetWriter attribute*), 160
`scales` (*rasterio.vrt.WarpedVRT attribute*), 201
`seek()` (*rasterio.io.MemoryFile method*), 166
`seek()` (*rasterio.io.ZipMemoryFile method*), 167
`Session` (*class in rasterio.session*), 183
`set_band_description()` (*rasterio.io.BufferedDatasetWriter method*), 135
`set_band_description()` (*rasterio.io.DatasetWriter method*), 160
`set_band_unit()` (*rasterio.io.BufferedDatasetWriter method*), 135
`set_band_unit()` (*rasterio.io.DatasetWriter method*), 161
`setenv()` (*in module rasterio.env*), 118
`shape` (*rasterio.io.BufferedDatasetWriter attribute*), 136
`shape` (*rasterio.io.DatasetReader attribute*), 149
`shape` (*rasterio.io.DatasetWriter attribute*), 161
`shape` (*rasterio.vrt.WarpedVRT attribute*), 201
`shape()` (*in module rasterio.windows*), 213
`shapes()` (*in module rasterio.features*), 124
`ShapeSkipWarning`, 120
`show()` (*in module rasterio.plot*), 172
`show_hist()` (*in module rasterio.plot*), 173
`show_versions_cb()` (*in module rasterio.rio.main*), 98
`sieve()` (*in module rasterio.features*), 124
`src_dataset` (*rasterio.vrt.WarpedVRT attribute*), 192
`src_nodata` (*rasterio.vrt.WarpedVRT attribute*), 192
`start()` (*rasterio.io.BufferedDatasetWriter method*), 136
`start()` (*rasterio.io.DatasetReader method*), 149
`start()` (*rasterio.io.DatasetWriter method*), 161
`start()` (*rasterio.vrt.WarpedVRT method*), 201
`statistics()` (*rasterio.io.BufferedDatasetWriter method*), 136
`statistics()` (*rasterio.io.DatasetReader method*), 149
`statistics()` (*rasterio.io.DatasetWriter method*), 161
`statistics()` (*rasterio.vrt.WarpedVRT method*), 201
`StatisticsError`, 120
`Stats` (*class in rasterio.rio.insp*), 97
`stats()` (*in module rasterio.rio.insp*), 97
`stop()` (*rasterio.io.BufferedDatasetWriter method*), 136
`stop()` (*rasterio.io.DatasetReader method*), 149
`stop()` (*rasterio.io.DatasetWriter method*), 161

S

`samp_den_coeff` (*rasterio.rpc.RPC attribute*), 175
`samp_num_coeff` (*rasterio.rpc.RPC attribute*), 175

`stop()` (*rasterio.vrt.WarpedVRT method*), 201
`subdatasets` (*rasterio.io.BufferedDatasetWriter attribute*), 136
`subdatasets` (*rasterio.io.DatasetReader attribute*), 149
`subdatasets` (*rasterio.io.DatasetWriter attribute*), 161
`subdatasets` (*rasterio.vrt.WarpedVRT attribute*), 201
`sum` (*rasterio.enums.Resampling attribute*), 113
`SwiftSession` (*class in rasterio.session*), 184

T

`tag_namespaces()` (*rasterio.io.BufferedDatasetWriter method*), 136
`tag_namespaces()` (*rasterio.io.DatasetReader method*), 149
`tag_namespaces()` (*rasterio.io.DatasetWriter method*), 161
`tag_namespaces()` (*rasterio.vrt.WarpedVRT method*), 202
`tags()` (*rasterio.io.BufferedDatasetWriter method*), 137
`tags()` (*rasterio.io.DatasetReader method*), 149
`tags()` (*rasterio.io.DatasetWriter method*), 162
`tags()` (*rasterio.vrt.WarpedVRT method*), 202
`tags_handler()` (*in module rasterio.rio.edit_info*), 96
`tastes_like_gdal()` (*in module rasterio.transform*), 190
`tell()` (*rasterio.io.MemoryFile method*), 166
`tell()` (*rasterio.io.ZipMemoryFile method*), 167
`ThreadEnv` (*class in rasterio.env*), 116
`to_authority()` (*rasterio.CRS method*), 217
`to_authority()` (*rasterio.crs.CRS method*), 105
`to_dict()` (*rasterio.CRS method*), 218
`to_dict()` (*rasterio.crs.CRS method*), 106
`to_dict()` (*rasterio.rpc.RPC method*), 175
`to_epsg()` (*rasterio.CRS method*), 218
`to_epsg()` (*rasterio.crs.CRS method*), 106
`to_gdal()` (*rasterio.rpc.RPC method*), 175
`to_lower()` (*in module rasterio.rio.helpers*), 97
`to_proj4()` (*rasterio.CRS method*), 218
`to_proj4()` (*rasterio.crs.CRS method*), 106
`to_string()` (*rasterio.CRS method*), 218
`to_string()` (*rasterio.crs.CRS method*), 106
`to_wkt()` (*rasterio.CRS method*), 219
`to_wkt()` (*rasterio.crs.CRS method*), 107
`todict()` (*rasterio.windows.Window method*), 210
`tolerance` (*rasterio.vrt.WarpedVRT attribute*), 192
`top` (*rasterio.coords.BoundingBox attribute*), 101, 102
`toranges()` (*in module rasterio.windows*), 213
`toranges()` (*rasterio.windows.Window method*), 210
`toslices()` (*rasterio.windows.Window method*), 210
`transform` (*rasterio.io.BufferedDatasetWriter attribute*), 137
`transform` (*rasterio.io.DatasetReader attribute*), 150
`transform` (*rasterio.io.DatasetWriter attribute*), 162
`transform` (*rasterio.vrt.WarpedVRT attribute*), 202

`transform()` (*in module rasterio.warp*), 206
`transform()` (*in module rasterio.windows*), 214
`transform_bounds()` (*in module rasterio.warp*), 207
`transform_geom()` (*in module rasterio.warp*), 207
`transform_handler()` (*in module rasterio.rio.edit_info*), 96
`TransformDirection` (*class in rasterio.enums*), 114
`TransformerBase` (*class in rasterio.transform*), 188
`TransformError`, 120
`TransformMethod` (*class in rasterio.enums*), 114
`TransformMethodsMixin` (*class in rasterio.transform*), 187
`TransformWarning`, 120

U

`undefined` (*rasterio.enums.ColorInterp attribute*), 110
`union()` (*in module rasterio.windows*), 214
`units` (*rasterio.io.BufferedDatasetWriter attribute*), 137
`units` (*rasterio.io.DatasetReader attribute*), 150
`units` (*rasterio.io.DatasetWriter attribute*), 162
`units` (*rasterio.vrt.WarpedVRT attribute*), 202
`units_factor` (*rasterio.CRS attribute*), 219
`units_factor` (*rasterio.crs.CRS attribute*), 107
`UnsupportedOperation`, 120
`update_tags()` (*rasterio.io.BufferedDatasetWriter method*), 137
`update_tags()` (*rasterio.io.DatasetWriter method*), 162

V

`validate_dtype()` (*in module rasterio.dtypes*), 109
`validate_length_value()` (*in module rasterio.windows*), 214

W

`warp_extras` (*rasterio.vrt.WarpedVRT attribute*), 193
`WarpedVRT` (*class in rasterio.vrt*), 191
`WarpedVRTError`, 120
`WarpOperationError`, 120
`WarpOptionsError`, 120
`webp` (*rasterio.enums.Compression attribute*), 111
`white` (*rasterio.enums.PhotometricInterp attribute*), 112
`width` (*in module rasterio.rio.overview*), 100
`width` (*rasterio.io.BufferedDatasetWriter attribute*), 137
`width` (*rasterio.io.DatasetReader attribute*), 150
`width` (*rasterio.io.DatasetWriter attribute*), 162
`width` (*rasterio.vrt.WarpedVRT attribute*), 202
`width` (*rasterio.windows.Window attribute*), 210
`Window` (*class in rasterio.windows*), 208
`window()` (*rasterio.io.BufferedDatasetWriter method*), 137
`window()` (*rasterio.io.DatasetReader method*), 150
`window()` (*rasterio.io.DatasetWriter method*), 162
`window()` (*rasterio.vrt.WarpedVRT method*), 202

`window()` (*rasterio.windows.WindowMethodsMixin method*), 210
`window_bounds()` (*rasterio.io.BufferedDatasetWriter method*), 138
`window_bounds()` (*rasterio.io.DatasetReader method*), 150
`window_bounds()` (*rasterio.io.DatasetWriter method*), 163
`window_bounds()` (*rasterio.vrt.WarpedVRT method*), 203
`window_bounds()` (*rasterio.windows.WindowMethodsMixin method*), 211
`window_index()` (*in module rasterio.windows*), 214
`window_transform()` (*rasterio.io.BufferedDatasetWriter method*), 138
`window_transform()` (*rasterio.io.DatasetReader method*), 151
`window_transform()` (*rasterio.io.DatasetWriter method*), 163
`window_transform()` (*rasterio.vrt.WarpedVRT method*), 203
`window_transform()` (*rasterio.windows.WindowMethodsMixin method*), 211
WindowError, 120
WindowEvaluationError, 120
WindowMethodsMixin (*class in rasterio.windows*), 210
`wkt` (*rasterio.CRS attribute*), 219
`wkt` (*rasterio.crs.CRS attribute*), 107
`WKT1` (*rasterio.enums.WktVersion attribute*), 114
`WKT1_ESRI` (*rasterio.enums.WktVersion attribute*), 114
`WKT1_GDAL` (*rasterio.enums.WktVersion attribute*), 114
`WKT2` (*rasterio.enums.WktVersion attribute*), 114
`WKT2_2015` (*rasterio.enums.WktVersion attribute*), 114
`WKT2_2019` (*rasterio.enums.WktVersion attribute*), 114
WktVersion (*class in rasterio.enums*), 114
`working_dtype` (*rasterio.vrt.WarpedVRT attribute*), 192
`write()` (*rasterio.io.BufferedDatasetWriter method*), 138
`write()` (*rasterio.io.DatasetWriter method*), 163
`write()` (*rasterio.io.MemoryFile method*), 166
`write()` (*rasterio.io.ZipMemoryFile method*), 167
`write_band()` (*rasterio.io.BufferedDatasetWriter method*), 138
`write_band()` (*rasterio.io.DatasetWriter method*), 163
`write_colormap()` (*rasterio.io.BufferedDatasetWriter method*), 138
`write_colormap()` (*rasterio.io.DatasetWriter method*), 164
`write_features()` (*in module rasterio.rio.helpers*), 97
`write_mask()` (*rasterio.io.BufferedDatasetWriter method*), 139
`write_mask()` (*rasterio.io.DatasetWriter method*), 164

`write_transform()` (*rasterio.io.BufferedDatasetWriter method*), 139
`write_transform()` (*rasterio.io.DatasetReader method*), 151
`write_transform()` (*rasterio.io.DatasetWriter method*), 164
`write_transform()` (*rasterio.vrt.WarpedVRT method*), 203

X

`xy()` (*in module rasterio.transform*), 190
`xy()` (*rasterio.io.BufferedDatasetWriter method*), 139
`xy()` (*rasterio.io.DatasetReader method*), 151
`xy()` (*rasterio.io.DatasetWriter method*), 164
`xy()` (*rasterio.transform.TransformerBase method*), 189
`xy()` (*rasterio.transform.TransformMethodsMixin method*), 188
`xy()` (*rasterio.vrt.WarpedVRT method*), 203

Y

`Y` (*rasterio.enums.ColorInterp attribute*), 110
`ycbcr` (*rasterio.enums.PhotometricInterp attribute*), 112
`yellow` (*rasterio.enums.ColorInterp attribute*), 110

Z

`ZipMemoryFile` (*class in rasterio.io*), 166
`zstd` (*rasterio.enums.Compression attribute*), 111